


HEALPix IDL Facilities Overview



Revision: Version 3.10; March 22, 2013

Prepared by: Eric Hivon, Anthony J. Banday, Benjamin D. Wandelt, Frode K. Hansen and Krzysztof M. Górski

Abstract: This document is an overview of the **HEALPix** IDL facilities.

TABLE OF CONTENTS

Using the HEALPix IDL facilities	5
Using HEALPix IDL together with other IDL libraries	5
Using GDL instead of IDL	5
What is available?	5
Maps related tools	5
Pixels related tools	6
Power spectrum, alm, beam and pixel window functions	6
Other	6
Changes between releases 3.00 and 3.10	7
Previous changes	7
alm_i2t	12
alm_t2i	14
alm2fits	16
ang2vec	19
angulardistance	21
azeqview	23
beam2bl	25
bin_llcl	27
bl2beam	29
bl2fits	31
cartcursor	33
cartview	34
change_polconv	36
cl2fits	39
convert_oldhpx2cmbfast	42
euler_matrix_new	44
fits2alm	46
fits2cl	49
gaussbeam	53
getdisc_ring	55
getsize_fits	56
gnomcursor	59

gnomview	60
healpix_doc: PDF and HTML documentation	63
healpixwindow	65
hpx2dm	67
hpx2gs	70
ianafast	73
index2lm	77
init_healpix and !healpix system variable	79
iprocess_mask	81
ismoothing	84
isynfast	87
lm2index	90
median_filter	91
mollcursor	93
mollview	96
neighbours_nest	112
neighbours_ring	114
npix2nside	116
nside2npix	118
nside2ntemplates	120
orthcursor	122
orthview	123
pix2xxx, ang2xxx, vec2xxx, nest2ring, ring2nest	125
query_disc	128
query_polygon	130
query_strip	132
query_triangle	134
read_fits_cut4	136
read_fits_map	138
read_fits_s	141
read_tqu	143
remove_dipole	146
reorder	149
rotate_coord	151

same_shape_pixels_XXXX	153
template_pixel_xxxx	156
ud_grade	158
vec2ang	161
write_fits_cut4	163
write_fits_map	167
write_fits_sb	170
write_tqu	174

Using the **HEALPix** IDL facilities

The current version of the **HEALPix** package provides an IDL startup file which defines various environment variables for your convenience, and adds the **HEALPix** IDL directory tree to your `IDL_PATH`. In order to utilise this feature, the user should invoke IDL using the commands `hidl` or `hidlde` which are aliases defined in the **HEALPix** profile created during the installation process for the package.

Using **HEALPix** IDL together with other IDL libraries

Many users want to use **HEALPix** IDL routines at the same time as other (home made or third party) IDL routines. There are several ways to achieve this.

Before starting `hidl` or `hidlde`, (re)define the environment variable `$IDL_PATH` so that it looks like: “`+/path/to/my/idl/routines:+/path/to/other/idl/routines:<IDL_DEFAULT>`” (where `<IDL_DEFAULT>` should be typed literally and the `+/path` means that subdirectories of *path* will be searched recursively). For example, if young Albert types in Bourne shell:

```
export IDL_PATH='+/home/aeinstein/brownian:<IDL_DEFAULT>'  
hidl
```

he will start an IDL session in which **HEALPix** IDL routines and all those located in subdirectories of `/home/aeinstein/brownian` are accessible.

Using GDL instead of IDL

See [the Installation Document](#) for more information on this issue.

What is available?

The **HEALPix**-IDL tools are mostly designed to generate, visualize, filter and analyze sky maps; identify, query and process **HEALPix** pixels; and deal with angular spectral objects (such as power spectra or Spherical Harmonics coefficients), as detailed below. The full documentation is available online in IDL via [healpix_doc](#)

HEALPix maps related tools

- Visualization: gnomonic, Mollweide, Cartesian, orthographic and azimuthal equatorial projections [mollview](#), [gnomview](#), [cartview](#), [orthview](#), [azeqview](#) (with interactive cursor: [cartcursor](#), [mollcursor](#), [gnomcursor](#), [orthcursor](#))
- production of **HEALPix** maps in Google Sky and Dome Master format [hpx2gs](#), [hpx2dm](#).

- Spherical Harmonics analysis and synthesis: `ianafast`, `isynfast`
- Smoothing and filtering: `ismoothing`, `median_filter`, `remove_dipole`
- Pixel pro/down-grading and NESTED/RING pixel reordering: `ud_grade`, `reorder`
- Mask processing: `iprocess_mask`
- Maps I/O: `read_fits_cut4`, `read_fits_map`, `read_fits_s`, `read_tqu`,
`write_fits_cut4`, `write_fits_map`, `write_fits_sb`, `write_tqu`,
`getsize_fits`, `change_polconv`

HEALPix pixels related tools

- Coordinate tools: `ang2vec`, `angulardistance`, `euler_matrix_new`, `rotate_coord`,
`vec2ang`
- Coordinates to pixel transforms, and back `nside2npix`, `npix2nside`, `ang2pix_*`,
`pix2ang_*`, `pix2vec_*`, `vec2pix_*`
- RING/NESTED transforms `nest2ring`, `ring2nest`
- Neighbouring pixels: `neighbours_nest`, `neighbours_ring`
- Pixel query within a disc, polygon, strip or triangle: `query_disc`, `query_polygon`,
`query_strip`, `query_triangle`.
- Template pixels: `nside2templates`, `same_shape_pixels_ring`,
`same_shape_pixels_nest`, `template_pixel_ring`, `template_pixel_nest`

Power spectrum, a_{lm} , beam and pixel window functions

- $B(l)$, $B(\theta)$ and pixel WF generation: `gaussbeam`, `beam2bl`, `bl2beam`, `healpixwindow`
- $C(l)$ binning: `bin_llcl`
- a_{lm} tools: `alm_i2t`, `alm_t2i`, `index2lm`, `lm2index`,
- $C(l)$, $B(l)$ and a_{lm} I/O: `fits2cl/cl2fits`, `bl2fits`, `fits2alm/alm2fits`,

Other

- HEALPix variables and paths initialization: `init_healpix`

Changes between releases 3.00 and 3.10

- Latest edition (version 3.10)
 - bug corrections: `query_disc`: correct handling of empty disc; `bin_llcl`: correct handling of optional argument.
 - double precision of input now preserved in `gaussbeam` and `euler_matrix_new`.
 - `fits2cl`: addition of `/PLANCK1` keyword to read best fit $C(l)$ model to Planck 2013 + external data.
 - it is now possible to read a specific FITS file extension identified by its (0-based) number or its case-insensitive EXTNAME value with the `Extension` keyword added to `fits2cl`, `getsize_fits`, `read_fits_map`, `read_fits_s` and `read_tqu`.
 - update of the required `IDL-astron library` routines, and their supporting `Coyote` routines (2013-02-08).

Previous changes

Changes between releases 2.20 and 3.00

- Previous edition (version 3.0)
 - New routines to go from circular beam profile to transfer function (`beam2b1`), and back (`b12beam`); to go from indexed list of a_{lm} to a(l,m) 2D table (`alm_i2t`), and back (`alm_t2i`); and to compute the angular distance between pairs of vectors (`angulardistance`).
 - addition of `iprocess_mask` interface to F90 `process_mask` facility to compute the angular distance of valid pixels to the closest invalid pixels for a input binary mask.
 - creation of `hpx2dm` routine to generate DomeMaster images of **HEALPix** maps that can be projected on planetariums.
 - the pixel query routines `query_triangle`, `query_polygon`, and in particular `query_disc`, have been improved and will return fewer false positive pixels in the *inclusive* mode
 - improved accuracy of the co-latitude calculation in the vicinity of the poles for high resolution in `nest2ring`, `ring2nest`, `pix2ang*`, `pix2vec*`, ...
 - `cartview`, `gnomview`, `mollview`, `orthview`: the length and spacing of the headless vectors used to represent polarization is now user-controlled via `POLARIZATION` keyword. The `COLT` keyword now allows the use of an interactively modified color table.
 - `orthview` now accepts `STAGGER` keyword to overplot staggered spheres (with a twist) in order to detect periodic boundary conditions on the sky
 - `fits2cl`: addition of `WMAP7` keyword to read best fit $C(l)$ model to WMAP 7yr data.
 - `read_fits_map` can now read $N_{\text{side}}=8192$ **HEALPix** maps and is generally faster than previously for smaller maps
 - update of `astron` library routines (01-Feb-2012).

Changes between release 2.0 and 2.20

Several routines have been added or improved since version 2.0, as listed below. Note that thanks to the newer IDL-`astron` library, FITS read/write routines in IDL-Healpix routines can now deal with **FITS files larger than 2GB** (on architectures supporting 64bit addressing).

Using 64 bit integers available since version 5.2 of IDL the maximum resolution parameter `Nside` supported has increased from $2^{13} = 8192$ to $2^{29} = 536870912$, corresponding to $3.46 \cdot 10^{18}$ pixels on the sphere.

- Recent edition (versions 2.20 and 2.20a)
 - `fits2cl`: addition of `WMAP1` and `WMAP5` keywords to read best fit $C(l)$ model to WMAP 1st and 5yr data respectively,
 - `cartview`, `gnomview`, `mollview`, `orthview`: the `OUTLINE` option now accept symbols with `PSYM > 8`, using `symcat` symbols definition.
- Recent editions (versions 2.15 and 2.15a)
 - `cartview`, `gnomview`, `mollview`, `orthview`:
 - * export of projected map into a FITS file (`FITS` keyword), or an IDL array (`MAP_OUT` option) now available with all viewing routines,
 - * added `CHARTHICK` support; accept array of `OUTLINE` structures (if they have the same fields), and still support structure of structures,
 - * correction of a bug (in `loaddata_healpix`) that was affecting the behavior of these viewing routines after consecutive calls with very partial cut-sky *and then* full-sky data sets [2.15a];
 - `remove_dipole` now outputs the monopole and dipole **covariance matrix**;
 - `write_fits_map`, `write_tqu`, `write_fits_sb`: `BAD_DATA` keyword added to FITS header;
 - update of `astron` library routines (24-May-2010) for improved WCS support.
- Previous edition (version 2.14a)
 - `cartview`, `gnomview`, `mollview`, `orthview`:
 - * `OUTLINE=`, `GRATICULE=`, `IGRATICULE=` work again with virtual windows (`WINDOW < 0`)
 - * `YPOS=` and `RETAIN=` keywords active again
 - * `PS=` keyword fixed
 - `orthview`: fixed problems with `/SHADE` keyword, which now outputs 8-byte (instead of 16-byte) PNG files
 - `ianafast`, `ismoothing`: fixed problem with processing of polarized maps stored in memory.
 - `ud_grade`: improved handling of flagged pixels on Double Precision input maps
 - `remove_dipole`: `COORD_IN=` and `COORD_OUT=` now accept lower case values; `/SILENT` keyword added.
- Old edition (version 2.13)
 - new `healpix.doc` routine to browse HTML and PDF documentations

- `cartview`, `gnomview`, `mollview`, `orthview`:
 - * introduction of the `TRUECOLORS=` keyword to generate color image from 3 channel map
 - * extended capability of the `TRANSPARENT=` keyword
 - * addition of `MAP_OUT=` to `gnomview`
- improved compatibility with `GDL` (free IDL clone). See “[HEALPix Installation Document](#)” for current `GDL` limitations.
- update of the `IDL-astrom` library routines, which now require IDL 6.1 or more
- `fits2alm`: new `LMAX=` and `LMIN=` keywords
- `fits2cl`: new `LLFACTOR=` keyword
- `init_healpix` defines substructure with complete path to **HEALPix** subdirectories (test, data, bin)
- slightly faster `write_fits_cut4` and `write_fits_sb` routines.
- `ianafast`, `ismoothing`: solved problem with `W8DIR=` keyword.
- Older editions (versions 2.11 and 2.12a)
 - `ianafast`, `ismoothing`, `isynfast`: the `TMPDIR` keyword now works properly, and `$IDL_TMPDIR` is used as the default temporary directory ; more stable behaviour of these routines
 - `ud_grade`:
 - * correctly flags bad output pixels with `bad_data` value when upgrading maps
 - * cut sky map: improved, faster routine, now works for `Nside > 8192`
 - `cartview`, `gnomview`, `mollview`, `orthview`:
 - * using a virtual window (ie, setting `WINDOW` to a negative value) now allows faster generation of GIF and PNG files (especially useful over remote connections);
 - * addition of `RETAIN=` keyword;
 - * deals correctly with user provided `MIN` and `MAX` in `LOG` and `ASINH` modes
 - * polarization norm map can be offset (`POLARIZATION=1` mode)
 - * original color table and plot settings are restored when leaving these routines
 - `orthview`: addition of `/SHADED` keyword for 3D rendering
 - issues warning when non-integer pixel indexes are fed to `nest2ring`, `ring2nest`, `pix2ang_*`, `pix2vec_*`, ...
 - `ximview`:
 - * fixed problem with cut-sky FITS files
 - * color scale bar added to PNG output
 - * version 0.6.2, fixed bug in pixel coordinates
 - cosmetic editions to `remove_dipole`
- New routines in version 2.10 include
 - `ximview`: visualisation routine developed by J. P. Leahy intended for quick-look inspection of HEALPix images (as well as ordinary 2-D images) at the level of individual pixels. Features include panning, zooming, blinking, image statistics and peak finding.
 - `hpx2gs`: turns a healpix data set into a [Google Earth](#)/[Google Sky](#)-compatible image
 - `ianafast`: interface to (F90) `anafast` and (C++) `anafast_cxx` facilities

- `isynfast`: interface to F90 `synfast` facility
- `ismoothing`: interface to F90 `smoothing` facility
- `bin_1l1l`: $C(l)$ binning
- `bl2fits`: writes $B(l)$ or $W(l)$ window into FITS file
- `neighbours_nest`, `neighbours_ring`: find immediate neighbours of a given pixel
- `query_strip`: find pixels lying within a colatitude strip
- Routines with extended/improved user interface or new functionalities include
 - `mollview`, `gnomview`, `cartview`, `orthview`:
 - * `ONLINE` keyword is now redundant,
 - * introduction of `GLSIZE` and `IGLSIZE` to control automatic labeling of graticules, see Fig. 2 on page 110
 - * addition of `SILENT` and `EXECUTE` keywords, see Fig. 2 on page 110
 - * addition of `ASINH` keyword to allow better visualisation of highly contrasted maps; see Figure 3 on page 111,
 - * under certain circumstances, can process high resolution cut sky data sets without creating full sky dummy maps,
 - * accept gzip compressed FITS files,
 - * accept polarized cut sky maps,
 - * accept multi-dimensional online arrays,
 - * more robust `OUTLINE` option.
 - `median_filter`: bugs correction
 - `ud_grade`: more robust user interface
 - `change_polcconv`: new `/FORCE` keyword
 - `remove_dipole`: more accurate
 - `query_disc`: when the disc center is located at one of the poles, *only* the pixels overlapping with the disc are now returned.
- Miscellaneous
 - `mollcursor`, `gnomcursor...`: an X11 patch is given so that these routines work under Mac OS X 10.4 and 10.5.

Changes between release 1.2 and 2.0

Some new routines have been introduced since version 1.2, as listed below. Most of the routines that already existed now have extended capabilities. Those of them with improved or extended user interface are listed below. They all remain backward compatible (ie, they can be used with codes written around version 1.1 and 1.2 without any edition).

- New routines in version 2.0 include
 - `median_filter`
 - `nside2templates`, `same_shape_pixels_ring`, `same_shape_pixels_nest`,
`template_pixel_ring`, `template_pixel_nest`

-
- `loaddata_healpix`: replaces `loaddata` to avoid conflict with other libraries
 - ...
 - Routines with extended/improved user interface or new functionalities include
 - `fits2cl`: addition of `/RSHOW`, `/SHOW` keywords to plot power spectra while they are read; possibility to read power spectra from a file containing a_{lm} coefficients.
 - `gnomview`, `mollview`, `orthview`, `cartview` faster FITS file reading (by up to a factor 6); can deal with WMAP polarized maps FITS format; extension of the `OUTLINE` keyword to plot set of points; addition of the `HBOUND` keyword to overplot pixel boundaries; ...
 - `read_tqu`, `read_fits_cut4`, `read_fits_map`: addition of output keywords `NSIDE`, `ORDERING`, `COORDSYS`
 - `reorder`: simpler interface to ordering conversion with addition of `/N2R` and `/R2N` keywords
 - `write_tqu`, `write_fits_cut4`, `write_fits_sb`: faster FITS file writing (by a factor 10 or more);
 - ...

alm_i2t

Location in HEALPix directory tree: `src/idl/misc/alm_i2t.pro`

This IDL function turns an indexed list of alm (as generated by `fits2alm`) into a tabular (real or complex) $a(l,m)$ array for easier manipulation

FORMAT IDL> `alm_table=alm_i2t(Index, Alm_vec, [/COMPLEX, /HELP, LMAX=, MMAX=])`

QUALIFIERS

Index	Integer vector of size n_i containing the index i of the of a_{lm} coefficients, related to $\{l,m\}$ by $i = l^2 + l + m + 1$
Alm_vec	Array of a_{lm} coefficients, with dimension $(n_i, n_{alm} [,n_{sig}])$ where n_i = number of i indices $n_{alm} = 2$ for real and imaginary parts of alm coefficients <i>or</i> 4 for above plus corresponding error values n_{sig} = number of signals (usually 1 for any of T E B or 3 for T,E,B together)

KEYWORDS

/COMPLEX	if set, the output array is complex with dimensions $(l_{max}+1, m_{max}+1, [n_{alm}/2, n_{sig}])$, otherwise, the array is real with dimensions $(l_{max}+1, m_{max}+1, n_{alm} [, n_{sig}])$. l_{max} and m_{max} are determined from input Index values, unless set otherwise by user.
/HELP	if set, prints out the help header and exits
LMAX=	l_{max} to be used in output array, regardless of value found in input index
MMAX=	m_{max} to be used in output array, regardless of value found in input index

DESCRIPTION `alm_i2t` returns a real or complex array, containing the a_{lm} with $0 \leq l \leq l_{\max}$ and $0 \leq m \leq m_{\max}$. The negative m are therefore ignored.

RELATED ROUTINES

This section lists the routines related to **`alm_i2t`**.

<code>idl</code>	version 6.1 or more is necessary to run <code>alm_i2t</code> .
<code>alm_t2i</code>	turns tabular alm's such as those generated by <code>alm_i2t</code> into indexed lists than can written to FITS files with <code>alm2fits</code>
<code>alm2fits, fits2alm</code>	routines to read and write a_{lm} indexed lists from and to FITS files.

EXAMPLE:

```
fits2alm, i1, a1, 'alm1.fits'
ac1 = alm_i2t(i1, a1, /complex, lmax=100, mmax=100)

fits2alm, i2, a2, 'alm2.fits'
ac2 = alm_i2t(i2, a2, /complex, lmax=100, mmax=100)

ac = 0.9*ac1 + 0.1*ac2

alm_t2i, ac, i, a
alm2fits, i, a, 'almsum.fits'
```

The example above reads 2 sets of a_{lm} from FITS files, puts the alm's with $(l,m) \leq 100$ in tabular arrays, and then make a weighted sum of the alm's. The resulting alm or put back into a indexed list in order to be written to FITS.

alm_t2i

Location in HEALPix directory tree: `src/idl/misc/alm_t2i.pro`

This IDL facility turns a tabular (real or complex) $a(l,m)$ array into an indexed list of alm that can be written into a FITS file with `alm2fits`

FORMAT IDL> `alm_t2i, Alm_table, Index, Alm_vec, [/HELP, /MFIRST]`

QUALIFIERS

Alm_table	Input real or complex array, containing all the a_{lm}^s for l in $[0, l_{\max}]$ and m in $[0, m_{\max}]$ (and s in $[0, s_{\max}]$ if applicable) if REAL it has 3 (or 4) dimensions, if COMPLEX it has 2 (or 3) dimensions
Index	Output integer vector of size <code>ni</code> containing the index i of the a_{lm} coefficients, related to $\{l, m\}$ by $i = l^2 + l + m + 1$
Alm_vec	Output array of a_{lm} coefficients, with dimension $(ni, 2 [s_{\max} + 1])$ where <code>ni</code> = number of i indices 2 for real and imaginary parts of alm coefficients $s_{\max} + 1$ = number of signals (usually 1 for any of T E B or 3 for T,E,B together)

KEYWORDS

<code>/HELP</code>	if set, prints out the help header and exits
<code>/MFIRST</code>	if set, the input array is $a(m,l)$ instead of $a(l,m)$

DESCRIPTION `alm_t2i` turns a real or complex tabular array of $a(l,m)$ (or $a(m,l)$ if `MFIRST` is set) into a real list of a_{lm} (with the real and imaginary parts separated) and its index $i = l^2 + l + m + 1$. The unphysical $m > l$ elements of the input table are dropped from the output list.

RELATED ROUTINES

This section lists the routines related to **alm_t2i**.

idl	version 6.1 or more is necessary to run alm_t2i.
alm_i2t	this function is complementary to alm_t2i and turns an indexed list of alm (as generated by fits2alm) into a tabular (real or complex) a(l,m) array for easier manipulation
alm2fits, fits2alm	routines to read and write a_{lm} indexed lists from and to FITS files.

EXAMPLE:

See **alm_i2t example**

alm2fits

Location in HEALPix directory tree: `src/idl/fits/alm2fits.pro`

This IDL routine provides a means to write spherical harmonic coefficients (and optional errors) and their index label to a FITS file. Each signal is written to a separate binary table extension. The routine also writes header information if required. The facility is primarily designed to allow the user to write a FITS files containing constraints for a constrained realisation performed by the **HEALPix** facility **synfast**.

FORMAT IDL> ALM2FITS, *index*, *alm_array*, *fitsfile*,
[HDR=, /HELP, XHDR=]

QUALIFIERS

<i>index</i>	Long array containing the index for the corresponding array of alm coefficients (and erralm if required). The index i is related to l, m by the relation $i = \ell^2 + \ell + m + 1$
<i>alm_array</i>	Real array of alm coefficients written to the file. This has dimension (nl,nalm,nsig) – corresponding to nl = number of l,m indices nalm = 2 for real and imaginary parts of alm coefficients or 4 for above plus corresponding error values nsig = number of signals to be written (1 for any of T E B or 3 if ALL to be written). Each signal is stored in a separate extension.
<i>fitsfile</i>	String containing the name of the file to be written.

KEYWORDS

HDR =	String array containing the primary header to be written in the FITS file.
-------	--

/HELP	If set, the routine documentation header is shown and the routine exits
XHDR =	String array containing the extension header. If ALL signals are required, then each extension table is given this header. NOTE: optional header strings should NOT include the header keywords explicitly written by this routine.

DESCRIPTION alm2fits writes the input alm coefficients (and associated errors if required) into a FITS file. Each signal type is written as a separate binary table extension. Optional headers conforming to the FITS convention can also be written to the output file. All required FITS header keywords are automatically generated by the routine and should NOT be duplicated in the optional header inputs. The keywords EXTNAME and TTYPE* are now also automatically generated.

RELATED ROUTINES

This section lists the routines related to **alm2fits**.

idl	version 6.1 or more is necessary to run alm2fits.
fits2alm	provides the complimentary routine to read in alm coefficients from a FITS file.
alm_i2t, alm_t2i	these facilities turn indexed lists of $a_{\ell m}$ into 2D a(l,m) tables and back
lm2index	converts the $a_{\ell m}$ order and degree (ℓ, m) into the index $i = \ell^2 + \ell + m + 1$ required by alm2fits.
cl2fits	routine to write a power spectrum into a FITS file.
fits2cl	routine to read/compute $C(l)$ power spectra from a file containing $C(l)$ or $a_{\ell m}$ coefficients
alteralm	utilises the output file generated by alm2fits.
synfast	utilises the output file generated by alm2fits.

EXAMPLE:

```
alm2fits, index, alm, 'alm.fits', HDR = hdr, XHDR = xhdr
```

alm2fits writes the coefficients stored in the variable `alm` to the output FITS file `alm.fits` with optional headers passed by the string variables `hdr` and `xhdr`.

ang2vec

Location in HEALPix directory tree: `src/idl/toolkit/ang2vec.pro`

This IDL facility convert the position angles of points on the sphere into their 3D position vectors.

FORMAT IDL> ANG2VEC , Theta, Phi, Vector [, ASTRO=]

QUALIFIERS

Theta	input: scalar or vector, colatitude in radians measured southward from north pole (in $[0, \pi]$). If ASTRO is set, Theta is the latitude in degrees measured northward from the equator (in $[-90, 90]$).
Phi	input: scalar or vector of same size as Theta, longitude in radians measured eastward (in $[0, 2\pi]$). If ASTRO is set, it is the longitude in degree measured eastward (in $[0, 360]$).
Vector	output : array, three dimensional cartesian position vector (x, y, z) normalised to unity. The north pole is $(0, 0, 1)$. The coordinates are ordered as follows $x(0), \dots, x(n-1)$, $y(0), \dots, y(n-1)$, $z(0), \dots, z(n-1)$

KEYWORDS

ASTRO =	if set Theta and Phi are the latitude and longitude in degrees instead of the colatitude and longitude in radians.
---------	--

DESCRIPTION `ang2vec` performs the geometrical transform from the position angles of points (θ, ϕ) into their position vectors (x, y, z) : $x = \sin \theta \cos \phi$, $y = \sin \theta \sin \phi$, $z = \cos \theta$

RELATED ROUTINES

This section lists the routines related to **`ang2vec`** .

idl	version 6.1 or more is necessary to run <code>ang2vec</code> .
<code>pix2xxx</code> , ...	conversion between vector or angles and pixel index
<code>vec2ang</code>	conversion from position vectors to angles

EXAMPLE:

```
lat = -45 ; latitude in degrees
long = 120 ; longitude in degrees
ang2vec, lat, lon, /astro, vec
```

will return in `vec` the 3D cartesian position vector of the point of latitude -45 deg and longitude 120 deg

angulardistance

Location in HEALPix directory tree: `src/idl/toolkit/angulardistance.pro`

This IDL facility computes the angular distance (in RADIANS) between pairs of vectors.

FORMAT IDL> distance=angulardistance(**V**, **W**,
[/HELP])

QUALIFIERS

V	3D-vector (of shape (3) or (1,3)) or list of n 3D-vectors (of shape (n,3))
W	3D-vector (of shape (3) or (1,3)) or list of n 3D-vectors (of shape (n,3))

It is **not** necessary for **V** and **W** vectors to be normalised to 1 upon calling the function

If **V** (and/or **W**) has the form (n,3,4) (like the pixel *corners* returned by `pix2vec_*`), it should be preprocessed with `V = reform(transpose(V, [0,2,1]), n_elements(V)/3, 3)` before being passed to angulardistance.

KEYWORDS

/HELP	if set, prints out the help header and exits
-------	--

DESCRIPTION After renormalizing the vectors, angulardistance computes the angular distance using $\cos^{-1}(\mathbf{V} \cdot \mathbf{W})$ in general, or $2 \sin^{-1}(\|\mathbf{V} - \mathbf{W}\|/2)$ when **V** and **W** are almost aligned.

If **V** (resp. **W**) is a single vector, while **W** (resp. **V**) is a list of vectors, then the result is a list of distances $d_i = \text{dist}(\mathbf{V}, \mathbf{W}_i)$ (resp. $d_i = \text{dist}(\mathbf{V}_i, \mathbf{W})$).

If both **V** and **W** are lists of vector *of the same length*, then the result is a list of distances $d_i = \text{dist}(\mathbf{V}_i, \mathbf{W}_i)$.

RELATED ROUTINES

This section lists the routines related to **angulardistance**.

idl version 6.1 or more is necessary to run angulardistance.

EXAMPLE:

```
nside=8  
pix2vec_ring, nside, lindgen(nside2npix(nside)), vpix  
mollview, angulardistance( vpix, [1,1,1])
```

will plot the angular distance between the Healpix pixels center for $N_{\text{side}} = 8$, and the vector $(x, y, z) = (1, 1, 1)/\sqrt{3}$

azeqview

Location in HEALPix directory tree: `src/idl/visu/azeqview.pro`

This IDL facility provides a means to visualise an azimuthal equidistant projection of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, JPEG, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

FORMAT

```
IDL> AZEQVIEW, File, [ Select, ] [ /ASINH,
CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP,
EXECUTE=, FACTOR=, FITS=, /FLIP, GAL_CUT=,
GIF=, GLSIZE=, GRATICULE=, /HALF_SKY, HBOUND=,
/HELP, /HIST_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-
ULE=, JPEG=, /LOG, MAP_OUT=, MAX=, MIN=,
/NESTED, /NO_DIPOLE, /NO_MONOPOLE, /NOBAR,
/NOLABELS, /NOPOSITION, OFFSET=, OUTLINE=,
PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZ=,
PYSIZ=, RESO_ARCMIN=, RETAIN=, ROT=, /SAVE,
/SHADED, /SILENT, STAGGER=, SUBTITLE=, TITLE-
PLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=,
WINDOW=, XPOS=, YPOS=]
```

QUALIFIERS

For a full list of qualifiers see [mollview](#)

KEYWORDS

For a full list of keywords see [mollview](#)

DESCRIPTION azeqview reads in a **HEALPix** sky map in FITS format and generates an azimuthal equidistant projection of it, that can be visualized on the screen or exported in a GIF, JPEG, PNG or Postscript file. azeqview allows the selection of the coordinate system, point of projection, map size, color table, color bar inclusion, linear or log scaling, histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc.* It also allows the representation of the polarization field.

RELATED ROUTINES

This section lists the routines related to **azeqview**.

	see mollview
hpx2dm	turns Healpix maps into DomeMaster images using azeqview.

beam2bl

Location in HEALPix directory tree: `src/idl/misc/beam2bl.pro`

This IDL facility computes a transfer (or window) function $b(l)$ for a circular beam profile $b(\theta)$.

FORMAT IDL> bl=beam2bl(*beam*, *theta*, *lmax*, [/ARCMIN , /DEGREES, /HELP, /RADIANS])

QUALIFIERS

beam	input beam profile $b(\theta)$
theta	angles θ (in arcmin, degrees or radians) at which the input beam $b(\theta)$ is defined
lmax	maximum multipole on which the output $b(l)$ is to be computed

KEYWORDS

/ARCMIN	if set, θ is in arcmin
/DEGREES	if set, θ is in degrees
/HELP	if set, prints out the help header and exits
/RADIANS	if set, θ is in radians

DESCRIPTION Since the SH Transform of an arbitrary beam is

$$b_{lm} = \int d\mathbf{r} \, b(\mathbf{r}) \, Y_{lm}^*(\mathbf{r}) \quad (1)$$

then, for a circular beam

$$\begin{aligned} b(l) &= b_{l0} \sqrt{\frac{4\pi}{2l+1}} \\ &= \int b(\theta) P_l(\theta) \sin(\theta) \, d\theta \, 2\pi \end{aligned} \quad (2)$$

where P_l is the Legendre Polynomial, $b(l)$ is the beam window (or transfer) function returned by `beam2bl` and $b(\theta)$ is the beam radial profile expected as input of `beam2bl`.

IDL's routine `INT_TABULATED` is used to perform the integration.

RELATED ROUTINES

This section lists the routines related to **beam2bl**.

idl	version 6.1 or more is necessary to run <code>beam2bl</code> .
bl2beam	facility to perform the inverse transform to <code>beam2bl</code> .
bl2fits	facility to write a $b(l)$ window function into a FITS file.
fits2cl	facility to read a $b(l)$ window function from a FITS file

EXAMPLE:

```
bl = gaussbeam(15.d0, 4000, 1)
theta = dindgen(4000)/100.
beam = bl2beam(bl, theta, /arcmin)
bl1 = beam2bl(beam, theta, 4000, /arcmin)
plot, bl1-bl
```

the example above generates a beam window function (defined for all l in $\{0, \dots, 4000\}$) for a 15arcmin-FWHM gaussian beam, computes the beam profile for angles in $[0, 40]$ arcmin, computes back the beam window function from the beam profile and finally plots the difference between the beam window functions.

bin_llcl

Location in HEALPix directory tree: `src/idl/misc/bin_llcl.pro`

This IDL facility provides a means to bin an angular power spectrum into arbitrary bins.

FORMAT IDL> BIN_LLCL, Llcl_in, Bin, L_out, Llcl_out, [Dllcl, DELTAL=, /FLATTEN, /HELP, /UNIFORM]

QUALIFIERS

Llcl_in	1D vector: input power spectrum (given for each l starting at 0).
Bin	input : binning in l to be applied, –either a scalar interpreted as the step size of a regular binning, the first bins are then $\{0, \text{bin} - 1\}, \{\text{bin}, 2\text{bin} - 1\}, \dots$ –or a 1D vector, interpreted as the lower bound of each bin, ie the first bins are $\{\text{bin}[0], \text{bin}[1] - 1\}, \{\text{bin}[1], \text{bin}[2] - 1\}, \dots$
L_out	contains on output the center of each bin l_b .
Llcl_out	contains on output the binned power spectrum $C(b)$, ie the (weighted) average of the input $C(l)$ over each bin.
Dllcl	optional , contains on output a rough estimate of the rms of the binned $C(l)$ for a full sky observation $C(b)\sqrt{2/((2l_b + 1)\Delta l_b)}$
DELTAL=	optional , contains on output the size of each bin $\Delta l(b)$

KEYWORDS

/FLATTEN if set, the $C(l)$ is internally multiplied by $l(l + 1)/2\pi$ before being binned.
 By default, the input `Llcl_in` is binned as is.

/HELP	if set, an extended help is printed and the code exits.
/UNIFORM	if set, the $C(l)$ in each bin is given the same weight. By default a weight $\propto 2l + 1$ is used (inverse cosmic variance weighting). Note that this weighting affects <code>Llcl_out</code> but not <code>L_out</code> .

DESCRIPTION `bin_llcl` bins the input power spectrum (as is, or after flattening by a $l(l+1)/2\pi$ factor) according to an arbitrary binning scheme defined by the user. Different weighting scheme (uniform or inverse variance) can be applied inside the bins.

RELATED ROUTINES

This section lists the routines related to `bin_llcl`.

idl	version 6.1 or more is necessary to run <code>bin_llcl</code> .
<code>fits2cl</code>	facility to read a power spectrum from a FITS file.

EXAMPLE:

```
init_healpix
fits2cl, cl, !healpix.directory+'/test/cl.fits', multipoles=1
fl = l*(l+1) / (2. * !pi)
bin_llcl, fl*cl[:,0], 10, lb, bbcb, /uniform
plot, 1, fl*cl[:,0]
oplot, lb, bbcb, psym = 4
```

Read a power spectrum, bin it with a binsize of 10 and a uniform weighting, and overplot the input spectrum and its binned version.

Location in HEALPix directory tree: `src/idl/misc/bl2beam.pro`

```
FORMAT      IDL> beam=bl2beam( bl, theta, [/ARCMIN ,  
                                /DEGREES, /HELP, /RADIANS])
```

theta angles θ (in arcmin, degrees or radians) at which the output beam $b(\theta)$ is to be computed.

/RADIANS if set, θ is in radians

DESCRIPTION Since an arbitrary beam is related to its SH Transform via

$$b(\mathbf{r}) = \sum_{lm} b_{lm} Y_{lm}(\mathbf{r}), \quad (3)$$

a circular beam has a radial profile (as returned by `bl2beam`)

$$b(\theta) = \sum_l b(l) P_l(\theta) \frac{2l+1}{4\pi}, \quad (4)$$

where P_l is Legendre Polynomial and

$$b(l) = b_{l0} \sqrt{\frac{4\pi}{2l+1}} \quad (5)$$

is the beam window (or transfer) function, expected as input to `bl2beam`.

RELATED ROUTINES

This section lists the routines related to `bl2beam`.

<code>idl</code>	version 6.1 or more is necessary to run <code>bl2beam</code> .
<code>beam2bl</code>	facility to perform the inverse transform to <code>bl2beam</code> .
<code>bl2fits</code>	facility to write a $b(l)$ window function into a FITS file.
<code>fits2cl</code>	facility to read a $b(l)$ window function from a FITS file

EXAMPLE:

```
bl = gaussbeam(15.d0, 4000, 1)
theta = dindgen(3000)/100.
beam = bl2beam(bl, theta, /arcmin)
plot, theta, beam
```

the example above generates a beam window function (defined for all l in $\{0, \dots, 4000\}$) for a 15arcmin-FWHM gaussian beam, computes the beam profile for angles in $[0, 30]$ arcmin and then plots it.

bl2fits

Location in HEALPix directory tree: `src/idl/fits/bl2fits.pro`

This IDL facility provides a means to write into a FITS file as an ascii table extension a (beam) window function $W(\ell)$ or $W(\ell)$. Adds additional headers if required. The facility is primarily intended to allow the user to write an arbitrary window function into a FITS file in the correct format to be ingested by the **HEALPix** simulation facility **synfast**.

FORMAT IDL> BL2FITS, bl_array, fitsfile, [HDR = ,
 /HELP, XHDR =]

QUALIFIERS

bl_array	real or double array of Bl coefficients to be written to file. This has dimension (lmax+1, <i>n</i>) with $1 \leq n \leq 3$, given in the sequence T E B.
fitsfile	String containing the name of the file to be written.

KEYWORDS

HDR =	String array containing the (non-trivial) primary header for the FITS file.
/HELP	If set, a help message is printed out, no file is written
XHDR =	String array containing the (non-trivial) extension header for the FITS file.

DESCRIPTION `bl2fits` writes the input $B(\ell)$ or $W(\ell)$ coefficients into a FITS file containing an ascii table extension. Optional headers conforming to the FITS convention can also be written to the output file. All required FITS header keywords (like SIMPLE, BITPIX, ...) are automatically generated by the routine and should NOT be duplicated in the optional header inputs (they would be ignored anyway). The one/two/three column(s) are automatically named **TEMPERATURE**, **GRAD**, **CURL** respectively. If the window function is provided in a double precision array, the output format will automatically feature more decimal places.

RELATED ROUTINES

This section lists the routines related to **bl2fits**.

idl	version 6.1 or more is necessary to run <code>bl2fits</code> .
<code>fits2cl</code>	provides the complimentary routine to read in a window function or power spectrum from a FITS file.
<code>synfast</code>	utilises the output file generated by <code>bl2fits</code> (option <code>beam_file</code>).

EXAMPLE:

```
beam1 = gaussbeam(10., 2000, 1)
beam2 = gaussbeam(15., 2000, 1)
beam = (beam1 + beam2) / 2.
bl2fits, beam, 'beam.fits'
```

`bl2fits` writes the beam window function stored in the variable `beam` (=Legendre transform of a circular beam) into the output FITS file `beam.fits`.

cartcursor

Location in HEALPix directory tree: `src/idl/visu/cartcursor.pro`

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a cartesian projection of a **HEALPix** map.

FORMAT IDL> `CARTCURSOR,` `[cursor_type=,`
 `file_out=]`

QUALIFIERS

see [mollcursor](#)

DESCRIPTION `cartcursor` should be called immediately after `cartview`. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by `orthview`. For more details, or in case of problems under **Mac OS X**, see [mollcursor](#).

RELATED ROUTINES

This section lists the routines related to **cartcursor**.

see [mollcursor](#)

EXAMPLE:

`cartcursor`

After `cartview` has read in a map and generated its cartesian projection, `cartcursor` is run to determine the position and flux of bright synchrotron sources, for example.

cartview

Location in HEALPix directory tree: `src/idl/visu/cartview.pro`

This IDL facility provides a means to visualise a cartesian projection (where the longitude and latitude are treated as the cartesian abscissa and ordinate) of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

FORMAT

```
IDL> CARTVIEW, File, [ Select, ] [ /ASINH,
CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP,
EXECUTE=, FACTOR=, FITS=, /FLIP, GAL_CUT=,
GIF=, GLSIZE=, GRATICULE=, /HALF_SKY, HBOUND=,
/HELP, /HIST_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-
ULE=, JPEG=, /LOG, MAP_OUT=, MAX=, MIN=,
/NESTED, /NO_DIPOLE, /NO_MONOPOLE, /NOBAR,
/NOLABELS, /NOPOSITION, OFFSET=, OUTLINE=,
PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZ=,
PYSIZ=, RESO_ARCMIN=, RETAIN=, ROT=, /SAVE,
/SHADED, /SILENT, STAGGER=, SUBTITLE=, TITLE-
PLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=,
WINDOW=, XPOS=, YPOS=]
```

QUALIFIERS

For a full list of qualifiers see [mollview](#)

KEYWORDS

For a full list of keywords see [mollview](#)

DESCRIPTION `cartview` reads in a **HEALPix** sky map in FITS format and generates a cartesian projection of it, that can be visualized on the screen or exported in a GIF, PNG or Postscript file. `cartview` allows the selection of the coordinate system, point of projection, map size, color table, color bar inclusion, linear or log scaling, histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc.* It also allows the representation of the polarization field.

RELATED ROUTINES

This section lists the routines related to **cartview**.

see [mollview](#)

EXAMPLE:

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
cartview,map,/online,res=45,graticule=[45,30],rot=[10,20,30],pysize=250,$
    title='Cartesian cylindrical (full sky)',subtitle='cartview', $
    outline=triangle
```

makes a cartesian cylindrical projection of map (see Figure [1a](#) on page [109](#)) after an arbitrary rotation, with a graticule grid (with a 45° step in longitude and 30° in latitude) and an arbitrary triangular outline

change_polconv

Location in HEALPix directory tree: `src/idl/fits/change_polconv.pro`

This IDL facility changes the coordinate convention in FITS file containing a polarised sky map. The main effect is to change the sign of the U Stokes parameter, and add/update the POLCCONV FITS header with either COSMO or IAU value.

FORMAT IDL> `CHANGE_POLCCONV` , File_In,
File_Out [, /I2C, /C2I, /C2C, /I2I, /FORCE]

QUALIFIERS

File_In	name of a FITS file to be read
File_Out	name of a FITS file to be written, after modification of the polarisation coordinate convention, if applicable

KEYWORDS

/I2C	changes from IAU to COSMO coordinate convention -if POLCCONV is not found or found with value 'IAU', it is added/replaced with value 'COSMO', and the sign of the U stokes parameter map is changed -if POLCCONV already has value 'COSMO', File_In is copied unchanged into File_Out
/C2I	changes from COSMO to IAU coordinate convention -if POLCCONV is not found or found with value 'COSMO', it is added/replaced with value 'IAU', and the sign of the U stokes parameter map is changed -if POLCCONV already has value 'IAU', File_In is copied unchanged into File_Out
/C2C	does NOT change coordinate system -if POLCCONV is found with value 'IAU', pro-

	gram will issue error message and no file is written
	-in all other case POLCCONV is set/added with value 'COSMO', but data is NOT changed
/I2I	does NOT change coordinate system
	-if POLCCONV is found with value 'COSMO', program will issue error message and no file is written
	-in all other case POLCCONV is set/added with value 'IAU', but data is NOT changed
/FORCE	if set, the value of POLCCONV read from the FITS header is ignored. The sign of U is swapped (if used with /C2I or /I2C), and the FITS keyword is updated accordingly.

DESCRIPTION This routine will change the sign of the U Stokes parameters (and related quantities, such as the TU and QU cross-correlations) and update the 'POLCCONV' FITS keyword where applicable. The recognised format are:

- standard Healpix full sky polarised format
- cut sky Healpix polarised format
- WMAP 2nd year polarised format

RELATED ROUTINES

This section lists the routines related to **change_polcconv** .

idl	version 6.1 or more is necessary to run change_polcconv
write_fits_cut4	This HEALPix IDL facility can be used to write a (polarised or unpolarised) cut sky map into a FITS file.
read_fits_cut4	This HEALPix IDL facility can be used to read a (polarised or unpolarised) cut sky map from a FITS file.
write_tqu	This HEALPix IDL facility can be used to write a polarised full sky map (with either the standard Healpix format or the WMAP 2nd year format) into a FITS file
read_tqu	This HEALPix IDL facility can be used to read

a polarised cut sky map from a FITS file

EXAMPLE:

```
change_polcconv, 'map_cosmo.fits', 'map_iau.fits', /c2i
```

Modify the file 'map_cosmo.fits', which was using the 'COSMO' convention for polarisation coordinate convention into 'map_iau.fits' which uses the 'IAU' convention

cl2fits

Location in HEALPix directory tree: `src/idl/fits/cl2fits.pro`

This IDL facility provides a means to write into a FITS file as an ascii table extension the power spectrum coefficients passed to the routine. Adds additional headers if required. The facility is primarily intended to allow the user to write a theoretical power spectrum into a FITS file in the correct format to be ingested by the **HEALPix** simulation facility **synfast**.

FORMAT IDL> CL2FITS, cl_array, fitsfile, [HDR=, /HELP, XHDR=, /CMBFAST, UNITS=]

QUALIFIERS

cl_array	real or double array of Cl coefficients to be written to file. This has dimension either (lmax+1,6) given in the sequence T E B Tx E Tx B Ex B or (lmax+1,4) given in the sequence T E B Tx E or (lmax+1) for T alone. The convention for the power spectrum is that it is not normalised by the Harrison-Zeldovich (flat) spectrum.
fitsfile	String containing the name of the file to be written.

KEYWORDS

HDR =	String array containing the (non-trivial) primary header for the FITS file.
/HELP	If set, a help message is printed out, no file is written
XHDR=	String array containing the (non-trivial) extension header for the FITS file.
/CMBFAST	if set, the routine will add the keyword 'POL-NORM = CMBFAST' in the FITS header, meaning that the polarization power spectra have the same convention as CMBFAST (and Healpix 1.2). If this keyword is not present in the input FITS

file, **synfast** will issue a warning when simulating a polarization map from that power spectrum, but no attempt to renormalize the power spectra will be made. To actually perform the renormalization, see **convert_oldhpx2cmbfast**

UNITS=

String scalar containing units of power spectrum (eg, uK^2 , Kelvin^2 , ...), to be put in keywords 'TUNIT*' of the extension header. If provided, will override the values present in XHDR (if any).

NOTE: optional header strings should NOT include the header keywords explicitly written by this routine.

DESCRIPTION **cl2fits** writes the input power spectrum coefficients into a FITS file containing an ascii table extension. Optional headers conforming to the FITS convention can also be written to the output file. All required FITS header keywords (like SIMPLE, BITPIX, ...) are automatically generated by the routine and should NOT be duplicated in the optional header inputs (they would be ignored anyway). The one/four/six column(s) are automatically named **TEMPERATURE**, **GRAD**, **CURL**, **G-T**, **C-T** and **C-G** respectively. If the power spectrum is provided in a double precision array, the output format will automatically feature more decimal places. The current implementation is much faster than the one available in Healpix 1.10 thanks to replacing an internal loop by vector operations.

RELATED ROUTINES

This section lists the routines related to **cl2fits**.

idl	version 6.1 or more is necessary to run cl2fits .
fits2cl	provides the complimentary routine to read in a power spectrum from a FITS file.
convert_oldhpx2cmbfast	convert an existing power spectrum FITS file from the polarization convention used in Healpix 1.1 to the one used in Healpix 1.2 (and CMBFAST).
bl2fits	facility to write a window function into a FITS file.

<code>fits2alm</code> , <code>alm2fits</code>	routines to read and write a_{lm} coefficients
<code>synfast</code>	utilises the output file generated by cl2fits.

EXAMPLE:

```
cl2fits, pwrsp, 'spectrum.fits', HDR = hdr, XHDR = xhdr
```

cl2fits writes the power spectrum stored in the variable `pwrsp` to the output FITS file `spectrum.fits` with optional headers passed by the string variables `hdr` and `xhdr`.

convert_oldhpx2cmbfast

Location in HEALPix directory tree: `src/idl/fits/convert_oldhpx2cmbfast.pro`

This IDL facility provides a means to change the normalization of polarization power spectra in a FITS file from Healpix 1.1 convention to Healpix 1.2 (which is the same as CMBFAST).

FORMAT IDL> CONVERT_OLDHPX2CMBFAST,
file_in, [file_out, NO_RENORM=]

QUALIFIERS

file_in	String containing the name of the FITS file with the power spectra to be read.
file_out	(OPTIONAL) String containing the name of the file to be written after renormalization. If absent, <code>file_in</code> will be used for output

KEYWORDS

NO_RENORM =	if set, the renormalization is not done. but the keyword POLNORM = CMBFAST is added to the FITS header (useful if the FITS file is already in CMBFAST format).
-------------	--

DESCRIPTION `convert_oldhpx2cmbfast` does the conversion from the polarization normalisation used in **HEALPix** 1.1 to the one used in **HEALPix** 1.2 (see the [Healpix primer document](#)). A keyword POLNORM = CMBFAST is added to the header to keep track of which files have been renormalized. If this keyword is not present in the input FITS file, **synfast** will issue a warning when simulating a polarization map from that power spectrum, but no attempt to renormalize the power spectra will be made.

RELATED ROUTINES

This section lists the routines related to **convert_oldhpx2cmbfast**.

idl	version 6.1 or more is necessary to run convert_oldhpx2cmbfast.
cl2fits	provides the a routine to write a power spectrum to a FITS file.
fits2cl	provides the complimentary routine to read in a power spectrum from a FITS file.
synfast	utilises the output file generated by convert_oldhpx2cmbfast.

EXAMPLE:

```
convert_oldhpx2cmbfast, 'cl_flat.fits'
```

convert_oldhpx2cmbfast will renormalize the polarization power spectra read from 'cl_flat.fits', and write them in the same file.

euler_matrix_new

Location in HEALPix directory tree: `src/idl/misc/euler_matrix_new.pro`

This IDL facility provides a means to generate a 3D rotation Euler matrix parametrized by three angles and three axes of rotation.

FORMAT IDL> matrix = EULER_MATRIX_NEW(a1, a2, a3 [, X=, Y=, ZYX=, DEG=])

QUALIFIERS

matrix	a 3x3 array containing the Euler matrix
a1	input, float scalar, angle of the first rotation, expressed in radians, unless DEG (see below) is set
a2	angle of the second rotation, same units as a1
a3	angle of the third rotation, same units as a1

KEYWORDS

DEG=	if set, the angles are in degrees instead of radians
X=	if set, uses the classical mechanics convention (ZXZ): rotation a1 around original Z axis, rotation a2 around intermediate X axis, rotation a3 around final Z axis (see Goldstein for more details). (default: this convention is used)
Y=	if set, uses the quantum mechanics convention (YZY): rotation a1 around original Z axis, rotation a2 around intermediate Y axis, rotation a3 around final Z axis.
ZYX=	if set, uses the aeronautics convention (ZYX): rotation a1 around original Z axis, rotation a2 around intermediate Y axis, rotation a3 around final X axis.

DESCRIPTION `euler_matrix_new` allows the generation of a rotation Euler matrix. The user can choose the three Euler angles, and the three axes of rotation.

If `vec` is an $N \times 3$ array containing N 3D vectors,
`vecr = vec # euler_matrix_new(a1,a2,a3,/Y)`
 will be the rotated vectors

This routine supersedes `euler_matrix`, which had inconsistent angle definitions. The relation between the two routines is as follows :

$$\begin{aligned} \text{euler_matrix_new}(a,b,c,/X) &= \text{euler_matrix}(-a,-b,-c,/X) \\ &= \text{Transpose}(\text{euler_matrix}(c, b, a,/X)) \end{aligned}$$

$$\begin{aligned} \text{euler_matrix_new}(a,b,c,/Y) &= \text{euler_matrix}(-a, b,-c,/Y) \\ &= \text{Transpose}(\text{euler_matrix}(c,-b, a,/Y)) \end{aligned}$$

$$\text{euler_matrix_new}(a,b,c,/Z) = \text{euler_matrix}(-a, b,-c,/Z)$$

RELATED ROUTINES

This section lists the routines related to **`euler_matrix_new`**.

<code>idl</code>	version 6.1 or more is necessary to run <code>euler_matrix_new</code> .
<code>rotate_coord</code>	apply a rotation to a set of position vectors and polarization Stokes parameters.

fits2alm

Location in HEALPix directory tree: `src/idl/fits/fits2alm.pro`

This IDL routine provides a means to read from a FITS file binary table extension(s) containing spherical harmonic coefficients $a_{\ell m}$ (and optional errors) and their index. Reads header information if required. The facility is intended to enable the user to read the output from the **HEALPix** facilities **anafast** and **synfast**.

FORMAT IDL> FITS2ALM, *index*, *alm_array*, *fitsfile*,
[*signal*, /HELP, HDR=, LMAX=, LMIN=,
XHDR=]

QUALIFIERS

<i>index</i>	Long array containing the index for the corresponding array of $a_{\ell m}$ coefficients (and errors if required). The index i is related to (l, m) by the relation $i = \ell^2 + \ell + m + 1.$ This has dimension <code>nl</code> (see below).
<i>alm_array</i>	Real or double array of alm coefficients read from the file. This has dimension <code>(nl,nalm,nsig)</code> – corresponding to <code>nl</code> = number of (l, m) indices <code>nalm</code> = 2 for real and imaginary parts of alm coefficients or 4 for above plus corresponding error values <code>nsig</code> = number of signals to be written (1 for any of T E B or 3 if ALL to be written). Each signal is stored in a separate extension.
<i>fitsfile</i>	String containing the name of the file to be read.
<i>signal</i>	String defining the signal coefficients to read Valid options: 'T', 'E', 'B' or 'ALL' (default: 'T').

KEYWORDS

HDR=	String array containing the primary header read from the FITS file.
/HELP	If set, the routine documentation header is shown and the routine exits
LMAX=	Largest l multipole to be output
LMIN=	Smallest l multipole to be output. If LMIN (resp. LMAX) is below (above) the range of l 's present in the file, it will be silently ignored
XHDR=	String array containing the read extension header(s). If ALL signals are required, then the three extension headers are returned appended into one string array.

DESCRIPTION fits2alm reads binary table extension(s) which contain the $a_{\ell m}$ coefficients (and associated errors if present) from a FITS file. FITS headers can also optionally be read from the input file.

RELATED ROUTINES

This section lists the routines related to **fits2alm**.

idl	version 6.1 or more is necessary to run fits2alm.
alm2fits	provides the complimentary routine to write $a_{\ell m}$ coefficients into a FITS file.
alm_i2t, alm_t2i	these facilities turn indexed lists of $a_{\ell m}$ into 2D $a(l,m)$ tables and back
index2lm	converts the index $i = \ell^2 + \ell + m + 1$ returned by fits2alm into ℓ and m
lm2index	converts (ℓ, m) vectors into $i = \ell^2 + \ell + m + 1$
fits2cl	routine to read/compute $C(l)$ power spectra from a file containing $C(l)$ or $a_{\ell m}$ coefficients
ianafast, isynfast	IDL routine providing $a_{\ell m}$ coefficients file to be read by fits2alm.
alteralm, anafast, synfast	F90 facilities providing $a_{\ell m}$ coefficients file to be read by fits2alm.

EXAMPLE:

```
fits2alm, index, alm, 'alm.fits', HDR = hdr, XHDR = xhdr
```

fits2alm reads from the input FITS file `alm.fits` the $a_{\ell m}$ coefficients into the variable `alm` with optional headers passed by the string variables `hdr` and `xhdr`. Upon return `index` will contain the value of $\ell^2 + \ell + m + 1$ for each $a_{\ell m}$ found in the file.

fits2cl

Location in HEALPix directory tree: `src/idl/fits/fits2cl.pro`

This IDL facility provides a means to read from a FITS file an ascii or binary table extension containing power spectrum ($C(l)$) or spherical harmonics (a_{lm}) coefficients, and returns the corresponding power spectrum ($C(l) = \sum_m a_{lm} a_{lm}^* / (2l + 1)$). Reads primary and extension headers if required. The facility is intended to enable the user to read the output from the HEALPix facility **anafast**.

FORMAT

```
IDL> fits2cl, cl_array, [fitsfile, EXTENSION=
, HDR= , /HELP, /INTERACTIVE, LL-
FACTOR=, MULTIPOLES=, /PLANCK1=,
/RSHOW, /SHOW, /SILENT=, /WMAP1=,
/WMAP5=, /WMAP7=, XHDR=]
```

QUALIFIERS

cl_array	real array of C_ℓ coefficients read or computed from the file. The output dimension depends on the contents of the file. This has dimension either (lmax+1,6) given in the sequence T E B TxE TxB ExB or (lmax+1,4) for T E B TxE or (lmax+1) for T alone. The convention for the power spectrum is that it is not normalised by the Harrison-Zeldovich (flat) spectrum.
fitsfile	String containing the name of the FITS file to be read. The file contains either $C(l)$ power spectra or a_{lm} coefficients. In either cases, $C(l)$ is returned. If <code>fitsfile</code> is not set, then <code>/PLANCK1</code> , <code>/WMAP1</code> , <code>/WMAP5</code> or <code>/WMAP7</code> must be set.

KEYWORDS

EXTENSION=	extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension <i>after</i>
------------	--

	primary array) or the case-insensitive value of its EXTNAME keyword.
HDR =	String array containing on output the primary header read from the FITS file.
/HELP	If set, produces an extended help message (using the doc.library IDL command).
/INTERACTIVE	If set, the plots generated by /SHOW and /RSHOW options are produced using iPlot routine, allowing for interactive cropping, zooming and annotation of the plots. This requires IDL 6.4 or newer to work properly.
LLFACTOR =	vector containing on output the factor $l(l+1)/2\pi$ which is often applied to $C(l)$ to flatten it for plotting purposes
MULTIPOLES =	vector containing on output the multipoles ℓ for which the power spectra are provided. They are either <ul style="list-style-type: none"> - read from the file (1st column in the Planck format), - or generated by the routine (assuming that all multipoles from 0 to lmax included are provided).
/PLANCK1	If set, and fitsfile is not provided, then a Planck 2013+external data best fit model (!healpix.path.test+'planck2013ext_lcdm_cl_v1.fits') defined up to lmax=4500, is read. See !healpix.path.test+'README' for details
/RSHOW	If set, the raw power spectra $C(l)$ read from the file are plotted
/SHOW	If set, the rescaled power spectra $l(l+1)C(l)/2\pi$ are plotted
/SILENT	If set, no message is issued during normal execution
/WMAP1	If set, and fitsfile is not provided, then one WMAP-1yr best fit model (!healpix.path.test+'wmap_lcdm_pl_model_yr1_v1.fits' which currently matches !healpix.path.test+'cl.fits') defined up to lmax=3000, is read. See !healpix.path.test+'README' for details
/WMAP5	If set, and fitsfile is not provided, then one WMAP-5yr best fit model (!healpix.path.test+

	'wmap_lcdm_sz_lens_wmap5_cl_v3.fits') defined up to lmax=2000, is read. See !healpix.path.test+'README' for details
/WMAP7	If set, and fitsfile is not provided, then one WMAP-7yr best fit model (!healpix.path.test+'wmap_lcdm_sz_lens_wmap7_cl_v4.fits') defined up to lmax=3726, is read. Note: As opposed to the other WMAP spectra mentionned above, it includes a non-vanishing B (or CURL) power spectrum induced by lensing of E (or GRAD) polarization. See !healpix.path.test+'README' for details
XHDR =	String array containing on output the extension header read from the FITS file.

DESCRIPTION fits2cl reads the power spectrum coefficients from a FITS file containing an ascii table extension. Descriptive headers conforming to the FITS convention can also be read from the input file.

RELATED ROUTINES

This section lists the routines related to **fits2cl**.

idl	version 6.1 or more is necessary to run fits2cl.
bin_llcl	facility to bin a spectrum read with fits2cl.
bl2fits	facility to write a window function into a FITS file.
cl2fits	provides the complimentary routine to write a power spectrum to a FITS file.
fits2alm, alm2fits	routines to read and write a_{lm} coefficients
ianafast	IDL routine computing $C(l)$ files that can be read by fits2cl.
anafast	F90 facility computing $C(l)$ files that can be read by fits2cl.

EXAMPLE:

```
fits2cl, pwrsp, '$HEALPIX/test/cl.fits', $  
          HDR=hdr, XHDR=xhdr, MULTI=1, LLFACT=fll  
plot, 1, powrsp[:,0]*fll
```

fits2cl reads a power spectrum $C(l)$ from the input FITS file `$HEALPIX/test/cl.fits` into the variable `pwrsp`, with optional headers passed by the string variables `hdr` and `xhdr`. The multipoles l and factors $l(l+1)/2\pi$ are read into `1` and `fll` respectively. $l(l+1)C(l)/2\pi$ vs l is then plotted.

gaussbeam

Location in HEALPix directory tree: `src/idl/misc/gaussbeam.pro`

This IDL facility provides the window function in ℓ space for a gaussian axisymmetric beam of given FWHM.

FORMAT IDL> beam=GAUSSBEAM (Fwhm, Lmax [, Dim])

QUALIFIERS

Fwhm	Full Width Half Maximum of the gaussian beam, in arcmin (scalar real)
Lmax	the window function is computed for the multipoles ℓ in $\{0,...,Lmax\}$
Dim	scalar integer, optional. If absent or set to 0 or 1, the output has size (Lmax+1) and is the temperature beam; if set to $2 \leq Dim \leq 4$, the output has size (Lmax+1,Dim) and contains in that order : the TEMPERATURE beam, the GRAD/ELECTRIC polarization beam the CURL/MAGNETIC polarization beam the TEMPERATURE*GRAD beam

DESCRIPTION gaussbeam computes the ℓ space window function of a gaussian beam of FWHM Fwhm. For a sky of underlying power spectrum $C(\ell)$ observed with beam of given FWHM, the measured power spectrum will be $C(\ell)_{meas} = C(\ell)B(\ell)^2$ where $B(\ell)$ is given by gaussbeam(Fwhm,Lmax). The polarization beam is also provided (when Dim > 1) assuming a perfectly co-polarized beam (eg, Challinor et al 2000, astro-ph/0008228)

RELATED ROUTINES

This section lists the routines related to **gaussbeam**.

idl	version 6.1 or more is necessary to run gaussbeam
healpixwindow	computes the ℓ space window function associated with a HEALPix pixel size
synfast	f90 code to generate CMB maps of given power spectrum convolved with a gaussian beam
smoothing	f90 code to smooth existing HEALPix maps with a gaussian beam
anafast	f90 code to compute the power spectrum of a HEALPix sky map

EXAMPLE:

```
beam = gaussbeam(5.,1200)
```

beam contains the window function in $\{0,...,1200\}$ of a gaussian beam of fwhm 5 arcmin

getdisc_ring

Location in HEALPix directory tree: `src/idl/toolkit/getdisc_ring.pro`

This routine is obsolete. Use `query_disc` instead.

getsize_fits

Location in HEALPix directory tree: `src/idl/fits/getsize_fits.pro`

This IDL function reads the number of maps and/or the pixel ordering of a FITS file containing a **HEALPix** map.

FORMAT IDL> var = GETSIZE_FITS (File, [Nmaps=, Nside=, Mlpol=, Ordering=, Obs_Npix=, Type=, Header=, Extension=, /Help])

QUALIFIERS

File	name of a FITS file containing the HEALPix map(s).
var	contains on output the number of pixels stored in a map FITS file. Each pixel is counted only once (even if several information is stored on each of them, see nmaps). Depending on the data storage format, result may be : <ul style="list-style-type: none"> – equal or smaller to the number Npix of Healpix pixels available over the sky for the given resolution ($N_{\text{pix}} = 12 * n_{\text{side}} * n_{\text{side}}$) – equal or larger to the number of non blank pixels (obs_npix)
Nmaps=	contains on output the number of maps in the file
Nside=	contains on output the HEALPix resolution parameter N_{side}
Mlpol=	contains on output the maximum multipole used to generate the map
Ordering=	contains on output the pixel ordering scheme: either 'RING' or 'NESTED'
Obs_Npix=	contains on output the number of non blank pixels. It is set to -1 if it can not be determined from header
Type=	Healpix/FITS file type <0 : file not found, or not valid 0 : image only fits file, deprecated Healpix format ($\text{var} = 12N_{\text{side}}^2$) 1 : ascii table, generally used for C(l) storage 2 : binary table : with implicit pixel indexing (full sky) ($\text{var} = 12N_{\text{side}}^2$) 3 : binary table : with explicit pixel indexing (generally cut sky) ($\text{var} \leq 12N_{\text{side}}^2$) 999 : unable to determine the type

Header=	contains on output the FITS extension header
Extension=	extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension <i>after</i> primary array) or the case-insensitive value of its EXTNAME keyword.

KEYWORDS

HELP=	if set, an extensive help is displayed and no file is read
-------	--

DESCRIPTION `getsize_fits` gets the number of pixels in a FITS file. If the file follows the **HEALPix** standard, the routine can also get the resolution parameter `Nside`, the ordering scheme, ..., and can determine the type of data set contained in the file.

RELATED ROUTINES

This section lists the routines related to `getsize_fits` .

idl	version 6.1 or more is necessary to run <code>getsize_fits</code>
<code>read_fits_map</code>	This HEALPix IDL facility can be used to read in maps written by <code>getsize_fits</code> .
<code>sxaddpar</code>	This IDL routine (included in HEALPix package) can be used to update or add FITS keywords to <code>Header</code>
<code>reorder</code>	This HEALPix IDL routine can be used to reorder a map from NESTED scheme to RING scheme and vice-versa.
<code>write_fits_sb</code>	routine to write multi-column binary FITS table

EXAMPLE:

```
npix = getsize_fits(!healpix.directory+'/test/map.fits', nside=nside, $
    mlpol=lmax, type=filetype)
print, npix, nside, lmax, filetype
```

should produce something like

196608 128 256 2

meaning that the map contained in that file has 196608 pixels, the resolution parameter is `nside=128`, the maximum multipole was 256, and this a full sky map (type 2).

gnomcursor

Location in HEALPix directory tree: `src/idl/visu/gnomcursor.pro`

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a gnomonic projection of a **HEALPix** map.

FORMAT IDL> GNOMCURSOR, [cursor_type=,
 file_out=]

QUALIFIERS

see [mollcursor](#)

DESCRIPTION gnomcursor should be called immediately after gnomview. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by gnomview. For more details, or in case of problems under **Mac OS X**, see [mollcursor](#).

RELATED ROUTINES

This section lists the routines related to **gnomcursor**.

see [mollcursor](#)

EXAMPLE:

gnomcursor

After gnomview has read in a map and generated its gnomonic projection, gnomcursor is run to determine the position and flux of bright synchrotron sources, for example.

gnomview

Location in HEALPix directory tree: `src/idl/visu/gnomview.pro`

This IDL facility provides a means to visualise a Gnomonic projection (radial projection onto a tangent plane) of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

FORMAT

```
IDL> GNOMVIEW,  File, [ Select, ] [ /ASINH,
CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP,
EXECUTE=, FACTOR=, FITS=, /FLIP, GAL_CUT=,
GIF=, GLSIZE=, GRATICULE=, /HALF_SKY, HBOUND=,
/HELP, /HIST_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-
ULE=, JPEG=, /LOG, MAP_OUT=, MAX=, MIN=,
/NESTED, /NO_DIPOLE, /NO_MONOPOLE, /NOBAR,
/NOLABELS, /NOPOSITION, OFFSET=, OUTLINE=,
PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZ=,
PYSIZ=, RESO_ARCMIN=, RETAIN=, ROT=, /SAVE,
/SHADED, /SILENT, STAGGER=, SUBTITLE=, TITLE-
PLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=,
WINDOW=, XPOS=, YPOS=]
```

QUALIFIERS

For a full list of qualifiers see [mollview](#)

KEYWORDS

For a full list of keywords see [mollview](#)

DESCRIPTION gnomview reads in a **HEALPix** sky map in FITS format and generates a Gnomonic projection of it, that can be visualized on the screen or exported in a GIF, PNG, Postscript or FITS file. gnomview allows the selection of the coordinate system, point of projection, map size, color table, color bar inclusion, linear or log scaling, histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc.* It also allows the representation of the polarization field.

RELATED ROUTINES

This section lists the routines related to **gnomview**.

see [mollview](#)

EXAMPLES: #1

```
gnomview, 'planck100GHZ-LFI.fits', rot=[160,-30], reso_arcmin=2., $
  pxsize = 500., $
  title='Simulated Planck LFI Sky Map at 100GHz', $
  min=-100,max=100
```

gnomview reads in the map 'planck100GHZ-LFI.fits' and generates an output image of the size of 500×500 screen pixels, with a resolution of 2 arcmin/screen pixel at the center. The temperature scale has been set to lie between ± 100 , and the units will show as μK . The title 'Simulated Planck LFI Sky Map at 100GHz' has been appended to the image. The map is centered at ($l=160$, $b=-30$)

EXAMPLES: #2

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
gnomview,map,/online,res=25,graticule=[45,30],rot=[10,20,30],$
  title='Gnomic projection',subtitle='gnomview', $
  outline=triangle
```

makes a gnomonic projection of map (see Figure 1b on page 109) after an arbitrary rotation, with a graticule grid (with a 45° step in longitude and 30° in latitude) and an arbitrary triangular outline

healpix_doc

Location in HEALPix directory tree: `src/idl/misc/healpix_doc.pro`

This IDL facility displays HTML or PDF **HEALPix** documentation

FORMAT IDL> healpix_doc, [HTML=| PDF=] [,
 HELP=, WHOLE=]

KEYWORDS

HELP=	if set, an extensive help on healpix_doc is displayed.
HTML=	if set, the HEALPix (IDL) HTML documentation is shown with a web browser. If the browser is already in use, a new tab is open.
PDF=	if set, the HEALPix (IDL) PDF documentation is shown with a pdf viewer. Either HTML or PDF must be set.
WHOLE=	if set, the whole HEALPix documentation is accessible, not just the IDL related part.

DESCRIPTION healpix_doc calls `Online_help` to open either the HTML or PDF **HEALPix** documentation. The browser and viewer used are those found by the `$IDL_DIR/bin/online_help_html` and `$IDL_DIR/bin/online_help_pdf` scripts respectively. The content of the `!healpix` system variable is used to determine the documentation path.

RELATED ROUTINES

This section lists the routines related to **healpix_doc**.

idl	version 6.1 or more is necessary to run healpix_doc.
-----	--

!HEALPIX

IDL system variable used by healpix_doc to locate the documentation.

EXAMPLES: #1

```
healpix_doc, /html, /whole
```

will open the whole **HEALPix** HTML documentation in a web browser.

EXAMPLES: #2

```
healpix_doc, /pdf
```

will open the IDL related **HEALPix** PDF documentation.

healpixwindow

Location in HEALPix directory tree: `src/idl/misc/healpixwindow.pro`

This IDL facility provides the window function in ℓ associated with the Healpix pixel of resolution Nside.

FORMAT IDL> wpix=HEALPIXWINDOW (Nside [, Dim, Directory])

QUALIFIERS

Nside	resolution parameter
Wpix	the pixel window function, computed for the multipoles ℓ in $\{0, \dots, 4N_{\text{side}}\}$
Dim	scalar integer, optional. If absent or set to 0 or 1, the output has size $(4N_{\text{side}}+1)$ and is the temperature window function; if set to $2 \leq \text{Dim} \leq 4$, the output has size $(4N_{\text{side}}+1, \text{Dim})$ and contains in that order : the TEMPERATURE window function, the GRAD/ELECTRIC polarization one the CURL/MAGNETIC polarization one the TEMPERATURE*GRAD one.
Directory	directory in which the precomputed pixel window file is looked for. (default: \$)HEALPIX/data/

DESCRIPTION `healpixwindow` computes the ℓ space window function due to the finite size of the **HEALPix** pixels. The typical size of a pixel (square root of its uniform surface area) is $\sqrt{3/\pi} \, 3600/N_{\text{side}}$ arcmin. If a unpixelised sky has a power spectrum $C(\ell)$, the same sky pixelised with a resolution parameter N_{side} will have the power spectrum $C(\ell)_{\text{pix}} = C(\ell)W(\ell)^2$ where $W(\ell)$ is given by `healpixwindow` (N_{side}). The polarized pixel window function is also provided (when $\text{Dim} > 1$). This routine reads some FITS files located in the subdirectory **data/** of the **HEALPix** distribution, unless the keyword **Directory** is set otherwise.

RELATED ROUTINES

This section lists the routines related to **healpixwindow**.

idl	version 6.1 or more is necessary to run <code>healpixwindow</code>
gaussbeam	computes the ℓ space window function associated with a gaussian beam
synfast	f90 code to generate CMB maps of given power spectrum at a given resolution (=pixel size)
anafast	f90 code to compute the power spectrum of a HEALPix sky map

EXAMPLE:

```
wpix = healpixwindow (256)
```

`wpix` contains the window function in $\{0, \dots, 1024\}$ of the **HEALPix** pixel with resolution parameter 256 (pixel size of 13.7 arcmin)

hpx2dm

Location in HEALPix directory tree: `src/idl/visu/hpx2dm.pro`

This IDL facility provides a means to turn a **HEALPix** data set into a DomeMaster compliant image (azimuthal equidistant projection of the half-sphere in a PNG or lossless JPEG file) that can be projected on a planetarium. See eg http://fulldome.ryanwyatt.net/fulldome_domemasterSpec_v05.pdf

FORMAT IDL> hpx2dm, **File**, [**Select**,] [**/HELP**,
JPEG=, **PNG=**, **PREVIEW=**, **PXSIZE=**, +
most of azeqview keywords...]

QUALIFIERS

File	Required name of a FITS file containing the HEALPix map in an extension or in the image field, <i>or</i> name of an <i>online</i> variable (either array or structure) containing the HEALPix map (See note below); if Save is set : name of an IDL saveset file containing the HEALPix map stored under the variable data (default: none)
Select	Optional column of the BIN FITS table to be plotted, can be either – a name : value given in TTYPEi of the FITS file NOT case sensitive and can be truncated, (only letters, digits and underscore are valid) – an integer : number i of the column containing the data, starting with 1 (also valid if File is an online array) (default: 1 for full sky maps, 'SIGNAL' column for FITS files containing cut sky maps)

KEYWORDS

JPEG=	name of the output <i>lossless</i> JPEG file
PNG=	name of the output PNG file
/PREVIEW	if set, the output JPEG or PNG file will be pre-viewed
/HELP	Prints out the documentation header
PXSIZE=	number of pixels in each dimension of the square output image
/ASINH,	
COLT=, COORD=, FACTOR=, /FLIP, HBOUND=,	
/HIST_EQUAL, /LOG, MAX=, MIN=, /NESTED, OFFSET=,	
/QUADCUBE, ROT=, SAVE=, /SILENT,	
TRUECOLORS=	those keywords have the same meaning as in aze-qview and mollview

DESCRIPTION hpx2dm reads in a **HEALPix** sky map in FITS format or from a memory array and generates a PNG or JPEG file containing a DomeMaster compliant map (azimuthal equidistant projection of the half-sky).

RELATED ROUTINES

This section lists the routines related to **hpx2dm**.

azeqview	performs Azimuthal Equidistant projection required by hpx2dm.
hpx2gs	turns Healpix maps into GoogleEarth or GoogleSky images

hpx2gs

Location in HEALPix directory tree: `src/idl/visu/hpx2gs.pro`

This IDL facility provides a means to turn a **HEALPix** map into a image that can be visualized with [Google Earth](#) or [Google Sky](#).

FORMAT	IDL> hpx2gs, File , [Select ,] [COORD_IN= , /HELP , KML= , PNG= , RESO_ARCMIN= , SUBTITLE= , TITLEPLOT= ,+ most of cartview keywords...]
---------------	--

QUALIFIERS

File	<p>Required</p> <p>name of a FITS file containing the HEALPix map in an extension or in the image field,</p> <p><i>or</i> name of an <i>online</i> variable (either array or structure) containing the HEALPix map (See note below);</p> <p>if Save is set : name of an IDL saveset file containing the HEALPix map stored under the variable data</p> <p>(default: none)</p>
Select	<p>Optional</p> <p>column of the BIN FITS table to be plotted, can be either</p> <ul style="list-style-type: none"> – a name : value given in TTYPEi of the FITS file <p>NOT case sensitive and can be truncated, (only letters, digits and underscore are valid)</p> <ul style="list-style-type: none"> – an integer : number i of the column containing the data, starting with 1 (also valid if File is an online array) <p>(default: 1 for full sky maps, 'SIGNAL' column for FITS files containing cut sky maps)</p>

KEYWORDS

COORD.IN =	<p>1-character scalar, describing the input data coordinate system:</p> <p>either 'C' or 'Q' : Celestial2000 = eQuatorial, 'E' : Ecliptic, 'G' : Galactic.</p> <p>If set, it will over-ride the coordinates read from the FITS file header (when applicable). In absence of information, the input coordinates is assumed to be celestial.</p> <p>The data will be rotated so that the output coordinates are Celestial, as expected by Google Sky</p>
/HELP	Prints out the documentation header
KML =	<p>Name of the KML file to be created (if the .kml suffix is missing, it will be added automatically)</p> <p>(default: 'hpx2googlesky.kml')</p>
PNG =	<p>Name of the PNG overlay file to be created. Only to be used if you want the filename to be different from the default ((default: same as KML file, with a .png suffix instead of .kml))</p>
RESO_ARCMIN =	Pixel angular size in arcmin (at the equator) of

the cartesian map generated (**default:** 30)

SUBTITLE = information on the data, will appear in KML file
GroundOverlay description field

TITLEPLOT = information on the data, will appear in KML file
GroundOverlay name field

/ASINH,
COLT=, FACTOR=, /FLIP, GLSIZE=, GRATICULE=, HBOUND=,
/HIST_EQUAL, IGLSIZE=, IGRATICULE=, /LOG, MAX=, MIN=,
/NESTED, OFFSET=,
OUTLINE=, POLARIZATION=, /PREVIEW,
/QUADCUBE, SAVE=, /SILENT,
TRUECOLORS= those keywords have the same meaning as in
cartview and mollview

DESCRIPTION hpx2gs reads in a **HEALPix** sky map in FITS format or from a memory array and generates a cartesian projection of it in a PNG file, as well as a Google Sky compatible **KML** file. Missing or unobserved pixels in the input data will be totally 'transparent' in the output file.

RELATED ROUTINES

This section lists the routines related to **hpx2gs**.

hpx2dm see **cartview**
turns Healpix maps into DomeMaster images

EXAMPLE:

```
map = findgen(48)
hpx2gs, map, kml='my_map.kml',title='my map in Google'
```

produces in **my_map.kml** and in **my_map.png** an image of the input map that can be seen with Google Sky. To do so, start GoogleEarth or GoogleSky and open **my_map.kml**. Under Mac-OSX, simply type **open my_map.kml** on the command line.

ianafast

Location in HEALPix directory tree: src/idl/interfaces/ianafast.pro

This IDL facility provides an interface to 'anafast' F90 and 'anafast_cxx' C++ facilities. It can be used to produce the Spherical Harmonics coefficients (a_{lm} of a **HEALPix** map (or pair of maps) and/or the resulting auto (or cross) power spectra $C(l)$.

FORMAT

```
IDL> IANAFAST, map1_in [, cl_out,
alm1_out=, alm2_out=, binpath=, cxx=,
double=, help=, healpix_data=, iter_order=,
keep_tmp_files=, map2_in=, maskfile=,
nested=, nlmax=, nmmax=, ordering=,
plmfile=, polarisation=, regression=,
ring=, show_cl=, simul_type=, silent=,
theta_cut_deg=, tmpdir=, weighted=, won=,
w8file=, w8dir=]
```

QUALIFIERS

map1_in	required input: 1st input map, can be a FITS file, or a memory array containing the map to analyze
cl_out	optional output: auto or cross power spectrum $C(l)$, can be a FITS file or a memory array

KEYWORDS

alm1_out=	output alm of 1st map, must be a FITS file (default: alm not kept)
alm2_out=	output alm of 2nd map (if any, must be a FITS file) (default: alm not kept)
binpath=	full path to back-end routine (default: \$HEXEXE/anafast,

	then \$HEALPIX/bin/anafast or \$HEALPIX/src/cxx/\$HEALPIX_TARGET- /bin/anafast_cxx, then \$HEALPIX/src/cxx/generic_gcc/bin/anafast_cxx if cxx is set) – a binpath starting with / (or \), or \$ is interpreted as absolute – a binpath starting with ./ is interpreted as relative to current directory – all other binpaths are relative to \$HEALPIX
/cxx	if set, the C++ back-end anafast_cxx is invoked instead of F90 anafast, AND the parameter file is written accordingly
/double	if set, I/O is done in double precision (default: single precision I/O)
/help	if set, prints extended help
healpix_data=	directory with Healpix precomputed files (only for C++ back_end when weighted=1) (default: \$HEALPIX/data)
iter_order=	order of iteration in the analysis (default: 0)
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
map2_in=	2nd input map (FITS file or array), if provided, Clout will contain the cross power spectra of the 2 maps (default: no 2nd map)
maskfile=	pixel mask (FITS file or array) (default: no mask)
/nested=	if set, signals that *all* maps and mask read online are in NESTED scheme (does not apply to FITS file), see also /ring and Ordering
nlmax=	maximum multipole of analysis, *required* for C++ anafast_cxx, optional for F90 anafast
nmmax=	maximum degree m, only valid for C++ anafast_cxx (default: nlmax)
ordering=	either 'RING' or 'NESTED', ordering of online maps and masks, see /nested and /ring
plmfile=	FITS file containing precomputed Spherical Har- monics (deprecated) (default: no file)
/polarisation	if set analyze temperature + polarization (same as simul_type = 2)

regression=	0, 1 or 2, regress out best fit monopole and/or dipole before alm analysis (default: 0, analyze raw map)
/ring	see /nested and ordering above
/show_cl	if set, and <code>cl_out</code> is defined, the produced $l(l+1)C(l)/2\pi$ will be plotted
simul_type=	1 or 2, analyze temperature only or temperature + polarization
/silent	if set, works silently
theta_cut_deg=	cut around the equatorial plane
tmpdir=	directory in which are written temporary files (default: IDL_TMPDIR (see IDL documentation))
/weighted	same as won (default: apply weighting)
/won	if set, a weighting scheme is used to improve the quadrature (default: apply weighting)
w8file=	FITS file containing weights (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing
w8dir=	directory where the weights are to be found (default: determined automatically by back-end routine)

DESCRIPTION ianafast is an interface to 'anafast' F90 and 'anafast_cxx' C++ facilities. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

RELATED ROUTINES

This section lists the routines related to **ianafast**.

idl	version 6.1 or more is necessary to run ianafast.
anafast	F90 facility called by ianafast.
anafast_cxx	C++ called by ianafast.
iprocess_mask	IDL Interface to F90 process_mask

<code>ismoothing</code>	IDL Interface to F90 smoothing
<code>isynfast</code>	IDL Interface to F90 synfast

EXAMPLE:

```
whitenoise = randomn(seed, nside2npix(256))
ianafast, whitenoise, cl, /ring, /silent
plot, cl[*,0]
```

will plot the power spectrum of a white noise map

index2lm

Location in HEALPix directory tree: `src/idl/misc/index2lm.pro`

This IDL routine provides a means to convert the $a_{\ell m}$ index $i = \ell^2 + \ell + m + 1$ (as returned by eg the `fits2alm` routine) into ℓ and m .

FORMAT IDL> INDEX2LM, index, l, m

QUALIFIERS

index	Long array containing on INPUT the index $i = \ell^2 + \ell + m + 1$.
l	Long array containing on OUTPUT the order ℓ . It has the same size as index .
m	Long array containing on OUTPUT the degree m . It has the same size as index .

DESCRIPTION `index2lm` converts $i = \ell^2 + \ell + m + 1$ into (ℓ, m) . Note that the index i is only defined for $0 \leq |m| \leq \ell$.

RELATED ROUTINES

This section lists the routines related to **index2lm**.

idl	version 6.1 or more is necessary to run <code>index2lm</code> .
<code>fits2alm</code>	reads a FITS file containing $a_{\ell m}$ values.
<code>alm2fits</code>	writes $a_{\ell m}$ values into a FITS file.
<code>lm2index</code>	routine complementary to <code>index2lm</code> : converts (ℓ, m) into $i = \ell^2 + \ell + m + 1$.

EXAMPLE:

```
index2lm, index, l, m
```

will return in `l` and `m` the order ℓ and degree m such that `index`
 $= \ell^2 + \ell m + m + 1$

init_healpix

Location in HEALPix directory tree: src/idl/misc/init_healpix.pro

This IDL facility creates an IDL system variable (!HEALPIX) containing various **HEALPix** related quantities

FORMAT IDL> INIT_HEALPIX [,VERBOSE=]

KEYWORDS

VERBOSE = if set, turn on the verbose mode, giving a short description of the variables just created.

DESCRIPTION init_healpix defines the IDL system variable and structure !HEALPIX containing several quantities and character string necessary to **HEALPix**, eg : allowed resolution parameters Nside, full path to package directory, package version...

RELATED ROUTINES

This section lists the routines related to **init_healpix**.

idl	version 6.1 or more is necessary to run init_healpix.
!HEALPIX	IDL system variable defined by init_healpix.

EXAMPLES: #1

```
init_healpix,/verbose
```

init_healpix will create the system variable !Healpix, and give a short description of the tags available, as shown below

Initializing !HEALPIX system variable

This system variable contains some information on Healpix :

!HEALPIX.VERSION = current version number,

!HEALPIX.DATE = date of release,

!HEALPIX.DIRECTORY = directory containing Healpix package,

!HEALPIX.PATH = structure containing:

!HEALPIX.PATH.BIN = structure containing binary path :

!HEALPIX.PATH.BIN.CXX = C++

!HEALPIX.PATH.BIN.F90 = Fortran90

!HEALPIX.PATH.DATA = path to data subdirectory,

!HEALPIX.PATH.DOC = path to doc subdirectories (.html, .pdf),

!HEALPIX.PATH.TEST = path to test subdirectory,

!HEALPIX.NSIDE = list of all valid values of Nside parameter,

!HEALPIX.BAD_VALUE = value of flag given to missing pixels in FITS files,

!HEALPIX.COMMENT = this description.

EXAMPLES: #2

help, !healpix, /structure

will print the content of the !Healpix system structure.

iprocess_mask

Location in HEALPix directory tree: `src/idl/interfaces/iprocess_mask.pro`

This IDL facility provides an interface to F90 'process_mask' facility. For a given input binary mask, it can determine the angular distance in Radians of each valid (1 valued) pixel to the closest invalid (0 valued) pixel, with the option of ignoring small clusters of invalid pixels. The distance map can then be used to generate an apodized mask.

FORMAT IDL> IPROCESS_MASK, `mask_in`, `distance_map`,[`binpath=`, `filled_mask=`, `/help`, `hole_arcmin2=`, `hole_pixels=`, `keep_tmp_files=`, `/nested`, `ordering=`, `/ring`, `/silent`, `tmpdir=`]

QUALIFIERS

<code>mask_in</code>	required input: input binary mask. It can be a FITS file, or a memory array containing the mask to process.
<code>distance_map</code>	optional output: double precision angular distance map in Radians. It can be a FITS file, or a memory array. It will have the same ordering as the input mask.

KEYWORDS

<code>binpath=</code>	full path to back-end routine (default: \$HEXE/process_mask, then \$HEALPIX/bin/process_mask) – a binpath starting with / (or \), or \$ is interpreted as absolute – a binpath starting with ./ is interpreted as relative to current directory – all other binpathes are relative to \$HEALPIX
<code>filled_mask=</code>	optional output mask with holes smaller than <code>hole_arcmin2</code> or <code>hole_pixels</code> filled in. Will have

	the same ordering as the input mask
/help	if set, prints extended help
hole_arcmin2	Minimal size (in arcmin ²) of invalid regions to be kept (can be used together with <code>hole_pixels</code> , the result will be the largest of the two). (default: 0.0)
hole_pixels	Minimal size (in pixels) of invalid regions to be kept (can be used together with <code>hole_arcmin2</code> , the result will be the largest of the two). (default: 0)
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
/nested	if set, signals that the mask read online is in NESTED scheme (does not apply to FITS file), see also <code>/ring</code> and <code>Ordering</code>
ordering=	either 'RING' or 'NESTED', ordering of online mask, see <code>/ring</code> and <code>/nested</code>
/ring	see <code>/nested</code> and <code>Ordering</code> above
/silent	if set, works silently
tmpdir=	directory in which are written temporary files (default: IDL_TMPDIR (see IDL documentation))

DESCRIPTION `iprocess_mask` is an interface to 'process_mask' F90 facility. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

RELATED ROUTINES

This section lists the routines related to `iprocess_mask`.

idl	version 6.1 or more is necessary to run <code>iprocess_mask</code> .
process_mask	F90 facility called by <code>iprocess_mask</code> .
<code>ianafast</code>	IDL Interface to F90 <code>anafast</code> and C++ <code>anafast_cxx</code>
<code>isynfast</code>	IDL Interface to F90 <code>synfast</code>

EXAMPLE:

```
npix = nside2npix(256)
mask = replicate(1, npix) & mask[randomu(seed,100)*npix] = 0
iprocess_mask, mask, distance, /ring, /silent
mollview, distance
```

A binary mask in which 100 randomly located pixels are 0-valued (=invalid) is generated. Then the distance (in Radians) of the valid pixels to the closest invalid pixels is computed and plotted.

ismoothing

Location in HEALPix directory tree: `src/idl/interfaces/ismoothing.pro`

This IDL facility provides an interface to F90 'smoothing' facility. It can be used to smooth a **HEALPix** map by an arbitrary circular 'beam' defined by its Legendre window function (or its FWHM if it is assumed Gaussian)

FORMAT IDL> ISMOOTHING, `map1_in`,
`map2_out`,[`beam_file=`, `binpath=`, `/double`,
`beam_arcmin=`, `/help`, `iter_order=`,
`keep_tmp_files=`, `lmax=`, `nlmax=`, `/nested`,
`ordering=`, `plmfile=`, `regression=`, `/ring`,
`simul_type=`, `/silent`, `theta_cut_deg=`, `tmpdir=`,
`/won`, `w8file=`, `w8dir=`]

QUALIFIERS

<code>map1_in</code>	required input: input map, can be a FITS file, or a memory array containing the map to smooth
<code>map2_out</code>	required output: output smoothed map, can be a FITS file, or a memory array

KEYWORDS

<code>beam_file=</code>	beam window function, either a FITS file or an array
<code>binpath=</code>	full path to back-end routine (default: <code>\$HEXEXE/smoothing</code> , then <code>\$HEALPIX/bin/smoothing</code>) – a binpath starting with <code>/</code> (or <code>\</code>), or <code>\$</code> is interpreted as absolute – a binpath starting with <code>./</code> is interpreted as relative to current directory – all other binpaths are relative to <code>\$HEALPIX</code>

/double	if set, I/O is done in double precision (default: single precision I/O)
fwhm_arcmin=	gaussian beam Full Width Half Maximum in arc-minutes (default: 0)
/help	if set, prints extended help
iter_order=	order of iteration in the analysis (default: 0)
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
lmax=, nlmax=	maximum multipole of smoothing (default: determined by back-end routine (ie, smoothing))
/nested	if set, signals that *all* maps and mask read online are in NESTED scheme (does not apply to FITS file), /ring and Ordering
ordering=	either 'RING' or 'NESTED', ordering of online maps and masks, see /ring and /nested
plmfile=	FITS file containing precomputed Spherical Harmonics (deprecated) (default: no file)
regression=	0, 1 or 2, regress out best fit monopole and/or dipole before alm analysis (default: 0, analyze raw map)
/ring	see /nested and Ordering above
simul_type=	1 or 2, analyze temperature only or temperature + polarization
/silent	if set, works silently
theta_cut_deg=	cut around the equatorial plane
tmpdir=	directory in which are written temporary files (default: IDL_TMPDIR (see IDL documentation))
/won	if set, a weighting scheme is used to improve the quadrature (default: apply weighting)
w8file=	FITS file containing weights (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing
w8dir=	directory where the weights are to be found (default: determined automatically by back-end routine)

DESCRIPTION ismoothing is an interface to 'smoothing' F90 facility. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

RELATED ROUTINES

This section lists the routines related to **ismoothing**.

idl	version 6.1 or more is necessary to run ismoothing.
smoothing	F90 facility called by ismoothing.
beam2bl	This IDL facility computes a transfer (or window) function $b(l)$ (such as the ones required by ismoothing) for a given circular beam profile $b(\theta)$
ianafast	IDL Interface to F90 anafast and C++ anafast_cxx
isynfast	IDL Interface to F90 synfast
iprocess_mask	IDL Interface to F90 process_mask

EXAMPLE:

```
whitenoise = randomn(seed, nside2npix(256))
ismoothing, whitenoise, rednoise, fwhm=120, /ring, simul=1,/silent
mollview, whitenoise, title='White noise'
mollview, rednoise, title='Smoothed white Noise'
```

will generate and plot a white noise map and its smoothed version

isynfast

Location in HEALPix directory tree: `src/idl/interfaces/isynfast.pro`

This IDL facility provides an interface to F90 'synfast' facility. It can be used to generate sky maps and/or a_{lm} from power spectra ($C(l)$), synthesize maps from a_{lm} or simulate maps from $C(l)$ and constraining a_{lm} .

FORMAT

IDL> ISYNFAST, cl_in [, map_out, alm_in=, alm_out=, apply_windows=, beam_file=, bin_path=, double=, fwhm_arcmin=, help=, iseed=, keep_tmp_files=, lmax=, nlmax=, nside=, nsmax=, plmfile=, simul_type=, silent=, tmpdir=, windowfile=, winfiledir=]

QUALIFIERS

cl_in	input power spectrum, can be a FITS file, or a memory array containing the $C(l)$, used to generate a map or a set of gaussian alm If empty quotes (") or a zero (0) are provided, it will be interpreted as "No input C(l)", in which case some input alm's (alm_in) are required.
map_out	optional output: <i>RING ordered</i> map synthetised from the power spectrum or from constraining alm

KEYWORDS

alm_in=	optional input (constraining) alm (must be a FITS file) (default: no alm)
alm_out=	contains on output the effective alm (must be a FITS file)
/apply_windows	if set, beam and pixel windows are applied to input alm_in (if any)
beam_file=	beam window function, either a FITS file or an array

binpath=	full path to back-end routine (default: \$HEXE/synfast, then \$HEALPIX/bin/synfast) – a binpath starting with / (or \), or \$ is interpreted as absolute – a binpath starting with ./ is interpreted as relative to current directory – all other binpaths are relative to \$HEALPIX
/double	if set, I/O is done in double precision (default: single precision I/O)
fwhm_arcmin=	gaussian beam FWHM in arcmin (default: 0)
/help	if set, prints extended help
iseed=	integer seed of random sequence (default: 0)
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
lmax=, nlmax=	maximum multipole simulation (default: $2*N_{\text{side}}$)
nside=, nsmax=	Healpix resolution parameter N_{side}
plmfile=	FITS file containing precomputed Spherical Harmonics (deprecated) (default: no file)
simul_type=	1) Temperature only 2) Temperature + polarisation 3) Temperature + 1st derivatives 4) Temperature + 1st & 2nd derivatives 5) T+P + 1st derivatives 6) T+P + 1st & 2nd derivatives (default: 2: T+P)
/silent	if set, works silently
tmpdir=	directory in which are written temporary files (default: IDL_TMPDIR (see IDL documentation))
windowfile=	FITS file containing pixel window (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing
winfiledir=	directory where the pixel windows are to be found (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing

DESCRIPTION isynfast is an interface to F90 'synfast' F90 facility. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

RELATED ROUTINES

This section lists the routines related to **isynfast**.

idl	version 6.1 or more is necessary to run isynfast.
synfast	F90 facility called by isynfast.
ianafast	IDL Interface to F90 anafast and C++ anafast_cxx
iprocess_mask	IDL Interface to F90 process_mask
ismoothing	IDL Interface to F90 smoothing

EXAMPLE:

```
isynfast, '$HEALPIX/test/cl.fits', map, fwhm=30, nside=256, /silent
mollview, map, 1, title='I'
mollview, map, 2, title='Q'
```

will synthesize and plot I and Q maps consistent with WMAP-1yr best fit power spectrum and observed with a circular gaussian 30 arcmin beam.

lm2index

Location in HEALPix directory tree: `src/idl/misc/lm2index.pro`

This IDL routine provides a means to convert the $a_{\ell m}$ degree and order (ℓ, m) into the index $i = \ell^2 + \ell + m + 1$ (in order to be fed to `alm2fits` routine for instance)

FORMAT IDL> LM2INDEX, l, m, index

QUALIFIERS

l	Long array containing on INPUT the order ℓ .
m	Long array containing on INPUT the degree m .
index	Long array containing on OUTPUT the index $i = \ell^2 + \ell + m + 1$.

DESCRIPTION `lm2index` converts (ℓ, m) into $i = \ell^2 + \ell + m + 1$. Note that by definition $0 \leq |m| \leq \ell$ (the routine does not check for this).

RELATED ROUTINES

This section lists the routines related to **lm2index**.

idl	version 6.1 or more is necessary to run <code>lm2index</code> .
<code>fits2alm</code>	reads a FITS file containing $a_{\ell m}$ values.
<code>alm2fits</code>	writes $a_{\ell m}$ values into a FITS file.
<code>index2lm</code>	routine complementary to <code>lm2index</code> : converts $i = \ell^2 + \ell + m + 1$ into (ℓ, m) .

EXAMPLE:

`lm2index, l, m, index`

will return in `index` in value $\ell^2 + \ell + m + 1$

median_filter

Location in HEALPix directory tree: `src/idl/toolkit/median_filter.pro`

This IDL facility allows the median filtering of a Healpix map.

FORMAT IDL> MEDIAN_FILTER (InputMap, Radius, MedianMap [,ORDERING=, /RING, /NESTED, /FILL_HOLES, /DEGREES, /ARCMIN])

QUALIFIERS

InputMap	(IN) either an IDL array containing a full sky Healpix map to filter ('online' usage), or the name of an external FITS file containing a full sky or cut sky map
Radius	(IN) radius of the disk on which the median is computed. It is in Radians, unless /DEGREES or /ARCMIN are set
MedianMap	(OUT) either an IDL variable containing on output the filtered map, or the name of an external FITS file to contain the map. Should be of same type of InputMap. Flagged pixels (ie, having the value !healpix.bad_value) are left unchanged, unless /FILL_HOLES is set.

KEYWORDS

/ARCMIN	If set, Radius is in arcmin rather than radians
/DEG	If set, Radius is in degrees rather than radians
/FILL_HOLES	If set, flagged pixels are replaced with the median of the valid pixels found within a distance Radius . If there are any.
/NESTED	Same as ORDERING='NESTED'
ORDERING=	Healpix map ordering, should be either 'RING' or 'NESTED'. Only applies to 'online' usage.

/RING Same as ORDERING='RING'

DESCRIPTION `median_filter` allows the median filtering of a Healpix map. Each pixel of the output map is the median value of the input map pixels found within a disc of given radius centered on that pixel. Flagged pixels can be either left unchanged or 'filled in' with that same scheme.

If the map is polarized, each of the three Stokes components is filtered separately.

The input and output can either be arrays or FITS files, but they to be both arrays or both FITS files.

RELATED ROUTINES

This section lists the routines related to **`median_filter`** .

idl version 6.1 or more is necessary to run `median_filter`

EXAMPLE:

```
median_filter ('map.fits', 10., /arcmin, 'med.fits')
```

Writes in 'med.fits' the median filtered map of 'map.fits' using a disc radius of 10 arcmin

EXAMPLE:

```
map = randomn(seed, nside2npix(256))
median_filter (map, 0.5, /deg, med)
```

Returns in `med` the median filtered map of `map` using a disc radius of 0.5 degrees

mollcursor

Location in HEALPix directory tree: src/idl/visu/mollcursor.pro

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a Mollweide projection of a **HEALPix** map.

FORMAT IDL> MOLLCURSOR, [cursor_type=,
 file_out=]

QUALIFIERS

cursor_type= cursor type to be used
 (default: 34)

file_out= file containing on output the list of point selected
 with the cursor.
 If set to 1, the file will take its default name: 'cur-
 sor_catalog.txt'.
 If set to a non-empty character string, the file
 name will be that string

DESCRIPTION `mollcursor` should be run immediately following `mollview`. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by `mollview`. Mouse buttons are used to select the function :

left button = display the information relative to the current cursor position,

middle button = print out this information in the IDL command window

right button = quit `mollcursor`

Note on Mac OS X, X11 and IDL cursor: on some versions^a of Mac OS X , starting with Tiger (ie, 10.4.*), the IDL function `cursor`, and therefore **HEALPix** `mollcursor`, `gnomcursor`, ... will not work properly under X11. To solve this problem, type under Tiger (10.4):

`defaults write com.apple.x11 wm_click_through -bool true`
or, under Leopard (10.5), Snow Leopard (10.6), Lion (10.7):

`defaults write org.x.x11 wm_click_through -bool true`
at your X11 prompt and restart X11 (tips found respectively at <http://marc.sauvage.free.fr/SAPMUG/Xnotes.html> and <https://sympa.obspm.fr/www/arc/micros-mac/2008-06/msg00001.html>). To make the patch permanent, add the line above into your `.bashrc` (or `.cshrc`, depending on your shell) file, and restart X11.

And finally, `mollcursor` obviously requires the '3 button mouse' to be enabled, which can be done in the X11 Preferences menu.

^athe command `sw_vers -productVersion` can be used to know the Mac OS X version being used

RELATED ROUTINES

This section lists the routines related to **`mollcursor`**.

<code>idl</code>	version 6.1 or more is necessary to run <code>mollcursor</code>
<code>ghostview</code>	<code>ghostview</code> or a similar facility is required to view the Postscript image generated by <code>mollcursor</code> .
<code>xv</code>	<code>xv</code> or a similar facility is required to view the GIF/PNG image generated by <code>mollcursor</code> (a browser can also be used).

synfast	This HEALPix facility will generate the FITS format sky map to be input to mollcursor.
cartview	IDL facility to generate a Cartesian projection of a HEALPix map.
cartcursor	interactive cursor to be used with cartview
gnomview	IDL facility to generate a gnomonic projection of a HEALPix map.
gnomcursor	interactive cursor to be used with gnomview
mollview	IDL facility to generate a Mollweide projection of a HEALPix map.
mollcursor	interactive cursor to be used with mollview
orthview	IDL facility to generate an orthographic projection of a HEALPix map.
orthcursor	interactive cursor to be used with orthview

EXAMPLE:

mollcursor

After mollview reads in a map and generates its mollweide projection, mollcursor is run to know the position and flux of bright synchrotron sources, for example.

mollview

Location in HEALPix directory tree: `src/idl/visu/mollview.pro`

This IDL facility provides a means to visualise a full sky Mollweide projection of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, JPEG, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

FORMAT

```
IDL> MOLLVIEW,  File, [ Select, ] [ /ASINH,
CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP,
EXECUTE=, FACTOR=, FITS=, /FLIP, GAL_CUT=,
GIF=, GLSIZE=, GRATICULE=, /HALF_SKY, HBOUND=,
/HELP, /HIST_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-
ULE=, JPEG=, /LOG, MAP_OUT=, MAX=, MIN=,
/NESTED, /NO_DIPOLE, /NO_MONOPOLE, /NOBAR,
/NOLABELS, /NOPOSITION, OFFSET=, OUTLINE=,
PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZ=,
PYSIZ=, RESO_ARCMIN=, RETAIN=, ROT=, /SAVE,
/SHADED, /SILENT, STAGGER=, SUBTITLE=, TITLE-
PLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=,
WINDOW=, XPOS=, YPOS=]
```

Several visualization routines have a similar interface. Their **qualifiers** and **keywords** are all listed here, and the routines to which they apply are coded in the 'routine' column as: A: **azeqview**, C: **cartview**, G: **gnomview**, M: **mollview**, O: **orthview** and all: all of them

Qualifiers should appear in the order indicated. They can take a range of values, and some of them are optional.

Keywords are optional, and can appear in any order. They take the form **keyword=value** and can be abbreviated to a non ambiguous form (ie, **factor=10.0** can be replaced by **fac = 10.0**). They generally can take a range of values, but some of them (noted as **/keyword**

below) are boolean switches: they are either present (or set to 1) or absent (or set to 0).

QUALIFIERS

name	routines	description
File	all	<p>Required</p> <p>name of a (possibly gzip compressed) FITS file containing the HEALPix map in an extension or in the image field, <i>or</i> name of an <i>online</i> variable (either array or structure) containing the (RING or NESTED ordered) HEALPix map (See note below);</p> <p>if Save is set : name of an IDL saveset file containing the HEALPix map stored under the variable data (default: none)</p> <p><u>Note on online data:</u> in order to preserve the integrity of the input data, the content of the array or structure File is replicated before being possibly altered by the map making process. Therefore plotting online data will require more memory than reading the data from disc directly, and is not recommended to visualize data sets of size comparable to that of the computer memory.</p> <p><u>Note on high resolution cut sky data:</u> cut sky data (in which less than 50% of the sky is observed), can be processed with a minimal memory foot-print, by not allocating fake full map. In the current release, two restrictions apply: the input data set must be read from a FITS file in 'cut4' format, and the POLARIZATION IDL keyword (described below) must be 0 (default value). See the Examples #4 below (on page 109).</p> <p>see also: TrueColors.</p>
Select	all	<p>Optional</p> <p>column of the BIN FITS table to be plotted, can be either</p> <ul style="list-style-type: none"> – a name : value given in TTYPEi of the FITS file <p>NOT case sensitive and can be truncated, (only letters, digits and underscore are valid)</p> <ul style="list-style-type: none"> – an integer : number i of the column containing the data, starting with 1 (also valid if File is an online array) <p>(default: 1 for full sky maps, 'SIGNAL' column for FITS files containing cut sky maps) (see the Examples below)</p>

KEYWORDS

name	routines	description
/ASINH	all	if set, the color table is altered to emulate the effect of replacing the data by $\sinh^{-1}(\text{data})$ in order to enhance the low contrast regions. Can be used in conjunction with Factor and Offset, but can <i>not</i> be used with /LOG nor /HIST_EQUAL. see also: Factor , Hist.Equal , Log , Offset
CHARSIZE=	all	overall multiplicative factor applied to the size of all characters appearing on the plot (default: 1.0)
CHARTHICK=	all	character thickness (in TITLE , SUBTITLE and color bar labeling). Other characters thickness (such as graticule labels), can be controlled with !P.CHARTHICK. (default: 1)
COLT=	all	color table index: <ul style="list-style-type: none"> – Indexes in [0,40] are reserved for standard IDL color tables, while [41,255] are used for user defined color tables read from disc (created and written to disc with MODIFYCT), if any. – If the index does not match any existing table, or if it is above 255, the current online table (modifiable with TVLCT, XLOADCT, XPALETTE, ... or eg, J. Davenport's cubehelix.pro implementation of D. Green's cubehelix color scheme) is used instead. – If <code>colt < 0</code>, the IDL color table <code>ABS(colt)</code> is used, but the scale is reversed (ie a red to blue scale becomes a blue to red scale). Note: -0.1 can be used as negative 0. (default: 33 (Blue-Red)) see also: TrueColors
COORD=	all	vector with 1 or 2 elements describing the coordinate system of the map; either <ul style="list-style-type: none"> – 'C' or 'Q' : Celestial2000 = eQuatorial, – 'E' : Ecliptic, – 'G' : Galactic if <code>coord = ['x','y']</code> the map is rotated from system 'x' to system 'y' if <code>coord = ['y']</code> the map is rotated to coordinate system 'y' (with the original system assumed to be Galactic unless indicated otherwise in the input file) see also: Rot
/CROP	all	if set the GIF/JPEG/PNG file only contains the map and no title, color bar, ... see also: Gif , Jpeg , Png

name	routines	description
EXECUTE=	all	character string containing IDL command(s) to be executed in the plotting window. See Figure 2 on page 110
FACTOR=	all	<p>scalar multiplicative factor to be applied to the valid data the data plotted is of the form $\text{Factor} * (\text{data} + \text{Offset})$</p> <p>This does not affect the flagged pixels</p> <p>Can be used together with ASINH or LOG</p> <p>When used with TRUECOLORS, FACTOR can be a 3-element vector.</p> <p>see also: ASINH, Offset, LOG, Truecolors (default: 1.0)</p>
FITS=	all	<p>string containing the name of an output FITS file with the projected map in the primary image</p> <ul style="list-style-type: none"> – if set to 1 : output the plot in <code>plot_proj.fits</code>, where <i>proj</i> is either <i>cartesian</i>, <i>gnomic</i>, <i>mollweide</i>, or <i>orthographic</i> depending on the projection in use; – if set to a file name : output the plot in that file. <p>(default: 0: no .FITS done)</p> <p>In the case of Orthographic projection, HALF_SKY must be set.</p> <p>Except for the color mapping, all the keywords and options apply to the projected map, ie: its size is determined by PX-SIZE (and PYSIZE when applicable), its angular resolution by RESO_ARCMIN when applicable, its orientation and coordinates by ROT and COORD respectively, ...</p> <p>For compatibility with standard FITS viewers (including STIFF), unobserved pixels, and pixels outside the sphere, take the value NaN (ie <code>!values.f_nan</code> in IDL). The resulting FITS file can be read in IDL with eg. <code>map=readfits(filename)</code>.</p> <p>see also: Map-out</p>
/FLIP	all	if set the longitude increases to the right, whereas by default (astronomical convention) it increases towards the left

name	routines	description
GAL_CUT=	—MO	(positive float) specifies the symmetric galactic cut in degrees outside of which the monopole and/or dipole fitting is done (default: 0: monopole and dipole fit done on the whole sky) (see also: No_dipole , No_monopole)
GIF=	all	string containing the name of a .GIF output if set to 1 : output the plot in plot_[projection].gif if set to a file name : output the plot in that file Please note that the resulting GIF image might not always look as expected. The reason for this is a problem with 'backing store' in the IDL-routine TVRD. Please read the IDL documentation for more information. (default: no .GIF done) see also: Crop , Jpeg , Png , Ps , Preview and Retain
GLSIZE=	all	character size of the graticule labels in units of Charsize . (default: 0: no labeling of graticules). see also: Charsize , Graticule
GRATICULE=	all	if set, puts a graticule (ie, longitude and latitude grid) in the <i>output</i> astrophysical coordinates with <code>delta_long = delta_lat = gdef</code> degrees if set to a scalar $x > \text{gmin}$ then <code>delta_long = delta_lat = x</code> if set to <code>[x,y]</code> with $x, y > \text{gmin}$ then <code>delta_long = x</code> and <code>delta_lat = y</code> cartview : <code>gdef = 45, gmin = 0</code> gnomview : <code>gdef = 5, gmin = 0</code> mollview : <code>gdef = 45, gmin = 10</code> orthview : <code>gdef = 45, gmin = 10</code> Note that the graticule will rotate with the sphere if <code>Rot</code> is set. To outline only the equator set <code>graticule=[360,90]</code> . The automatic labeling of the graticule is controlled by Glsiz (default: 0 [no graticule]) see also: Igraticule , Rot , Coord , Glsiz

name	routines	description
/HALF_SKY	—O	if set, only shows only one half of the sky (centered on (0,0) or on the location parametrized by Rot) instead of the full sky
HBOUND=	all	scalar or vector of up to 3 elements. If Hbound[i] is set to a valid N_{side} , the routine will overplot the HEALPix pixel boundaries corresponding to that N_{side} on top of the map. The first N_{side} will be plotted with solid lines, the second one (if any) with dashes and the third one (if any) with dots. Obviously, better results are obtained for Hbounds elements in growing order. Since 0-valued boundaries are not plotted, but used for linestyle assignment, providing Hbound=[0,4] (or [0,0,4]) will plot $N_{\text{side}} = 4$ boundaries with dashes (resp. dots), while Hbound=4 would plot the same boundaries with solid lines.
/HELP	all	if set, the routine header is printed (by doc_library) and nothing else is done
/HIST_EQUAL	all	if set, uses a histogram equalized color mapping (useful for non gaussian data field) (default: uses linear color mapping and puts the level 0 in the middle of the color scale (ie, green for Blue-Red) unless Min and Max are not symmetric) see also: Asinh , Log
HXSIZE=	all	horizontal dimension (in cm) of the Postscript printout (default: 26 cm \simeq 10 in) see also: Pxsize
IGLSIZE=	all	character size of the input coordinates graticule labels in units of Charsize . (default: 0: no labeling of graticules). see also: Charsize , Igraticule
IGRATICULE=	all	if set, puts a graticule (ie, longitude and latitude grid) in the <i>input</i> astrophysical coordinates. See Graticule for conventions and details. If both Graticule and Igraticule are set, the latter will be represented with dashes. The automatic labeling of the graticule is controlled by Iglsize (default: 0 [no graticule]) see also: Graticule , Rot , Coord , Iglsize
JPEG=	all	string containing the name of a <i>lossless</i> .JPEG output file if set to 1 : output the plot in plot_[projection].jpeg if set to a file name : output the plot in that file (default: no .JPEG done) see also: Crop , Fits , Gif , Map_out , Png , Preview Ps , and Retain

name	routines	description
/LOG	all	display the log of map. This is intended for application to positive definite maps only, eg. Galactic foreground emission templates; for arbitrary maps, use /ASINH instead. see also: Asinh , Factor , Hist.Equal , Offset
MAP_OUT=	all	variable that will contain the projected map on output. Except for the color mapping, all the keywords and options apply to the projected map, ie: its size is determined by PX-SIZE (and PYSIZE when applicable), its angular resolution by RESO_ARCMIN when applicable, its orientation and coordinates by ROT and COORD respectively, ... Unobserved pixels, and pixels outside the sphere, take value !healpix.bad_value ($= -1.6375 \cdot 10^{30}$). see also: Fits
MAX=	all	Set the maximum value for the plotted signal (default: is to use the actual signal maximum).
MIN=	all	Set the minimum value for the plotted signal (default: is to use the actual signal minimum).
/NESTED	all	specify that the online data is ordered in the nested scheme
/NO_DIPOLE	—MO	if set (and Gal.cut is not set) the best fit monopole *and* dipole over all valid pixels are removed; if Gal.cut is set to $b > 0$, the best monopole and dipole fit is performed on all valid pixels with $ \text{galactic latitude} > b$ (in deg) and is removed from all valid pixels (default: 0 (no monopole or dipole removal)) can NOT be used together with No_monopole see also: Gal.cut , No_monopole
/NO_MONOPOLE—MO		if set (and Gal.cut is not set) the best fit monopole over all valid pixels is removed; if Gal.cut is set to $b > 0$, the best monopole fit is performed on all valid pixels with $ \text{galactic latitude} > b$ (in deg) and is removed from all valid pixels (default: 0 (no monopole removal)) can NOT be used together with No_dipole see also: Gal.cut , No_dipole
/NOBAR	all	if set, color bar is not present
/NOLABELS	all	if set, color bar labels (min and max) are not present, (default: labels are present)
/NOPOSITION	—G—	if set, the astronomical location of the map central point is not indicated

name	routines	description
OFFSET=	all	<p>scalar additive factor to be applied to the valid data the data plotted is of the form $\text{Factor} * (\text{data} + \text{Offset})$</p> <p>This does not affect the flagged pixels</p> <p>can be used together with ASINH or LOG</p> <p>When used with TRUECOLORS, OFFSET can be a 3-element vector.</p> <p>see also: : ASINH, Factor, LOG, TRUECOLORS (default: 0.0)</p>
OUTLINE=	all	<p>IDL structure, structure of structures, or array of structures, containing the description of one (or several) outline(s) to be overplotted on the final map.</p> <p>For each contour or point list, the corresponding (sub)structure should contain the following fields :</p> <ul style="list-style-type: none"> – 'COORD' coordinate system (either, 'C', 'G', or 'E') of the contour – 'RA' RA/longitude coordinates of the contour vertices (array or scalar) – 'DEC' Dec/latitude coordinates of the contour vertices (array or scalar) – 'LINE[STYLE]' (optional, scalar) +2: black dashes, +1: black dots, 0: black solid (default), -1: black dots on white background, -2: black dashes on white background – 'PSY[M]' (optional, scalar) symbol used to represent vertices (same meaning as standard PSYM in IDL. If $9 \leq \text{psym} \leq 46$, D. Fanning's cgSYMCAT.PRO symbols definition will be used; for example, psym=9 is an open circle). If ≤ 0, the vertices are represented with the chosen symbols, and connected by arcs of geodesics; if > 0, only the vertices are shown (default: 0) – 'SYM[SIZE]' (optional, scalar) vertice symbol size (same meaning as SYMSIZE in IDL) <p>Notes: when applicable, the vertices are connected by segments of geodesics. To obtain a better looking outline, increase the number of vertices provided. The outline does not have to be closed. The procedure will NOT attempt to close the outline. Several outlines can be overplotted at once by gathering the respective structures into one meta-structure or an array.</p> <p>see also: Coord, Graticule</p>

name	routines	description
PNG=	all	<p>string containing the name of a .PNG output if set to 1 : output the plot in plot_[projection].png if set to a file name : output the plot in that file Please note that the resulting PNG image might not always look as expected. The reason for this is problems with 'backing store' in the IDL-routine TVRD. Please read the IDL documentation for more information. (default: no .PNG done) see also: Crop, Fits, Gif, Jpeg, Map_out, Preview Ps, and Retain</p>
POLARIZATION=all		<p>if set to</p> <ul style="list-style-type: none"> 0 no polarization information is plotted. 1 the AMPLITUDE $P = \sqrt{U^2 + Q^2}$ of the polarization is plotted (as long as the input data contains polarization information (ie, Stokes parameter Q and U for each pixel)) 2 the ANGLE $\phi = \tan^{-1}(U/Q)/2$ of the polarization is plotted Note: the angles are color coded with a fixed color table (independent of Colt) 3 –the temperature is color coded (with a color table defined by Colt) –and the polarization is overplotted as headless VECTORS Polarization can then be a 3-element vector (the first element being 3). The second element controls the average length of vectors (default: 1), while the third one controls the distance between vectors (default: 1). Non-positive values are replaced by 1. (default: 0) <p>Note: The representation of the polarization direction (options 2 and 3 above), include the effects of the rotations and/or changes or astronomical coordinates (controlled by ROT and COORD respectively) but do not include the effects of the distortions induced by the projection from the sphere to the plan. Because the polarization usually has more power at small scales, it must generally be represented on maps of small patches of the sky to remain legible, in which case the projection-induced distortions are small.</p>

name	routines	description
/PREVIEW	all	if set, there is a 'ghostview' preview of the postscript file or a 'xv' preview of the gif file see also: Gif , Jpeg , Png and Ps
PS=	all	if set to 0 : no postscript output if set to 1 : output the plot in plot_cartesian.ps, plot_gnomonic.ps, plot_mollweide.ps or plot_orthographic.ps respectively if set to a file name : output the plot in that file (default: 0) see also: Preview , Gif , Jpeg , Png
PXSIZE=	all	set the number of horizontal screen_pixels or postscript_color_dots of the plot (useful for high definition color printer) or elements of the output map (default: 800 (Mollview and full sky Orthview), 600 (half sky Orthview), 500 (Cartview and Gnomonic)) see also: FITS , GIF , JPEG , MAP_OUT , PNG , PS .
PYSIZE=	ACG-	set the number of vertical screen_pixels or postscript_color_dots of the plot (default: Pxsize).
RESO_ARCMIN=	ACG-	size of screen_pixels or postscript_color_dots in arcmin (default: 1.5) see also: FITS , GIF , JPEG , MAP_OUT , PNG , PS .
RETAIN=	all	specifies the type of backing store to use for direct graphics windows in {0,1,2}. (default: 2). See IDL documentation for details.
ROT=	all	vector with 1, 2 or 3 elements specifying the rotation angles in DEGREES to apply to the map in the 'output' coordinate system (see Coord) = (lon0, [lat0, rat0]) lon0 : longitude of the point to be put at the center of the plot the longitude increases Eastward, ie to the left of the plot (default: 0) lat0 : latitude of the point to be put at the center of the plot (default: 0) rot0 : anti clockwise rotation to apply to the sky around the center (lon0, lat0) before projecting (default: 0)

name	routines	description
/SAVE	all	if set, assumes that File is in IDL saveset format, the variable saved should be DATA
/SHADED	—O	if set, the orthographic sphere is shaded, using a Phong model, to emulate 3D viewing. The sphere is illuminated by isotropic ambient light plus a single light source. Can NOT be used with GIF .
/SILENT	all	if set, the program runs silently
STAGGER=	—O	Scalar or 2 element vector: <ul style="list-style-type: none"> – if stagger[0] is in]0,2], three copies of the same sphere centered respectively at [-stagger[0], 0, stagger[0]] (expressed in radius units) along the plot horizontal axis are shown in ORTHOGRAPHIC projection – if set, stagger[1] defines the angle of rotation (in degrees) applied to the left and right partial spheres: the <i>lhs</i> sphere is rotated downward by the angle provided, while the <i>rhs</i> one is rotated upward. Rotations are swapped if FLIP is set. Currently can not be used with Graticule nor igraticule
SUBTITLE=	all	String containing the subtitle to the plot see also: Titleplot
TITLEPLOT=	all	String containing the title of the plot, if not set the title will be File see also: Subtitle
TRANSPARENT=all		If set to 1, the input data pixels with value !healpix.bad_value ($= -1.6375 \cdot 10^{30}$) will appear totally transparent on the output PNG file (instead of the usual grey). If set to 2, the background pixels will be transparent (instead of the usual white) If set to 3, both the grey and white pixels will look transparent. Active only in conjunction with PNG

name	routines	description
TRUECOLORS=	all	<p>if the input data is of the form [Npix,3], then the 3 fields are respectively understood as Red, Green, Blue True-Color channels, and the color table is ignored.</p> <ul style="list-style-type: none"> – If set to 1, the mapping field-intensity to color is done for the 3 channels at once. (see also: Factor, Offset) – If set to 2, that mapping is done for each channel separately (in that case, MIN and MAX keywords are ignored).
UNITS=	all	String containing the units, to be put on the right hand side of the color bar, overrides the value read from the input file, if any see also: Nobar , Nolabels
WINDOW=	all	<p>IDL window index (integer)</p> <ul style="list-style-type: none"> – if WINDOW < 0: virtual window: no visible window opened. Can be used with PNG, JPEG, or GIF, in particular is those files are larger than the screen. Note: The Z buffer will be used instead of the X server, allowing much faster production of the image over a slow network – if WINDOW in [0,31]: the specified IDL window with index WINDOW is used (or reused). Can be used to have a sequence of images appear in the same window – if WINDOW > 31: a free (=unused) window with a random index > 31 will be created and used. <p>(default: 32)</p>
XPOS=	all	The X position on the screen of the lower left corner of the window, in device coordinate
YPOS=	all	The Y position on the screen of the lower left corner of the window, in device coordinate

DESCRIPTION mollview reads in a **HEALPix** sky map in FITS format and generates a Mollweide projection of it, that can be visualized on the screen or exported in a PNG, JPEG or Postscript file. mollview allows the selection of the coordinate system, map size, color table, color bar inclusion, linear or log scaling, histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc.* It also allows the representation of the polarization field.

RELATED ROUTINES

This section lists the routines related to **mollview**.

idl	version 6.1 or more is necessary to run mollview
ghostview	ghostview or a similar facility is required to view the Postscript image generated by mollview.
xv	xv or a similar facility is required to view the GIF/JPEG/PNG image generated by mollview (a browser can also be used).
synfast, smoothing	These F90 HEALPix facilities will generate the FITS format sky maps to be input to mollview.
isynfast, ismoothing	These IDL routines will generate the FITS format sky maps to be input to mollview.
cartview	IDL facility to generate a Cartesian projection of a HEALPix map.
cartcursor	interactive cursor to be used with cartview
gnomview	IDL facility to generate a gnomonic projection of a HEALPix map.
gnomcursor	interactive cursor to be used with gnomview
mollview	IDL facility to generate a Mollweide projection of a HEALPix map.
mollcursor	interactive cursor to be used with mollview
orthview	IDL facility to generate an orthographic projection of a HEALPix map.
orthcursor	interactive cursor to be used with orthview

EXAMPLES: #2

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
mollview,map, graticule=[45,30],rot=[10,20,30],$
    title='Mollweide projection',subtitle='mollview', $
    outline=triangle
```

makes a Mollweide projection of a pixel index map (see Figure 1c on page 109) after an arbitrary **rotation**, with a **graticule** grid (with a 45° step in longitude and 30° in latitude) and an arbitrary (triangular) **outline**




Figure 1: Figures produced by `cartview`, `gnomview`, `mollview` and `orthview`, see respective routine documentation for details.

EXAMPLES: #3

```
map = findgen(48)
mycommand = 'x=findgen(64)/10.  & ' + $
           'plot,x,sin(x),pos=[0.8,0.8,0.99,0.99],/noerase &' + $
           'xyouts,0.5,0.5,' 'Hello World !'',/normal,charsize=2,align=0.5'
mollview,map, execute=mycommand, png='plot_example_execute.png',/preview,$
        /graticule,/glsize
```

produces a PNG file containing a Mollweide projection of a pixel index map with labeled graticules, a simple sine wave in the upper right corner, and some greetings, as shown on Figure 2 on page 110

EXAMPLES: #4




Figure 2: Figure produced by example #3.

```

pixel = 164indgen(400000)
signal = pixel * 10.0
file = 'cutsky.fits'
write_fits_cut4, file, pixel+100000, signal, nside=32768, /ring
gnomview, file, rot=[0,90], grat=30, title='high res. cut-sky map'

```

produces and plots a high resolution map (6.4 arcsec/pixel), in which only a very small subset of pixels is observed

EXAMPLES: #5

```

file = 'wmap_band_iqumap_r9_5yr_K_v3.fits'
mollview, file, title='Linear Color Scale', /silent
mollview, file,/asinh,title='Sinh!u-1!n Color Scale' , /silent
mollview, file,/hist, title='Histogram Equalized Color Scale', /silent
mollview, file,/log, title='Log Scale', /silent

```

produces Mollweide projections of the same map (here the WMAP-5yr K band) with various color scales: linear, Inverse Hyperbolic Sine, Histogram Equalized, and Log. See Figure 3 on page 111

EXAMPLES: #1




Figure 3: Illustration (generated by example #5) of the various color scales available.

```
mollview, 'planck100GHZ-LFI.fits', min=-100, max=100, /graticule, $
title='Simulated Planck LFI Sky Map at 100GHz'
```

mollview reads in the map 'planck100GHZ-LFI.fits' and generates an output image in which the temperature scale has been set to lie between ± 100 (μK), a **graticule** with a 45 degree step in longitude and latitude is drawn, and the **title** 'Simulated Planck LFI Sky Map at 100GHz' appended to the image.

	idl	version 6.1 or more is necessary to run neighbours_nest .
	neighbours_ring	returns topological immediate neighbouring pixels of a given central pixel, using RING indexing.
	query_disc, query_polygon, query_strip, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle
	nest2ring, ring2nest	conversion between NESTED and RING indices

EXAMPLE:

```
neighbours_nest , 4, 1, list, nneigh
print,nneigh,list
```

will return:8 90 0 2 3 6 4 94 91, listing the NESTED-indexed 8 neighbors of pixel #1 for Nside=4

<code>neighbours_nest</code>	returns topological immediate neighbouring pixels of a given central pixel, using NESTED indexing.
<code>query_disc, query_polygon, query_strip, query_triangle</code>	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle
<code>nest2ring, ring2nest</code>	conversion between NESTED and RING indices

EXAMPLE:

```
neighbours_ring , 4, 1, list, nneigh
print,nneigh,list
```

will return: 8 16 6 5 0 3 2 8 7 listing the RING-indexed 8
neighbors of pixel #1 for Nside=4

npix2nside

Location in HEALPix directory tree: `src/idl/toolkit/npix2nside.pro`

This IDL facility provides the **HEALPix** resolution parameter `Nside` corresponding to `Npix` pixels over the full sky.

FORMAT IDL> `Nside=NPIX2NSIDE (Npix [,ERROR=])`

QUALIFIERS

<code>Npix</code>	number of pixels over the full sky (scalar integer), should be a valid <code>Npix</code> ($N_{\text{pix}} = 12N_{\text{side}}^2$ with N_{side} power of 2 in $\{1, \dots, 2^{29}\}$)
<code>Nside</code>	on output: resolution parameter if <code>Npix</code> is valid, -1 otherwise

KEYWORDS

<code>ERROR =</code>	error flag, set to 1 on output if <code>Npix</code> is NOT valid, or stays to 0 otherwise.
----------------------	--

DESCRIPTION `npix2nside` checks that the given `Npix` is valid ($N_{\text{pix}} = 12N_{\text{side}}^2$ with N_{side} a power of 2 in $\{1, \dots, 2^{29}\}$) and then computes the corresponding resolution parameter N_{side} .

RELATED ROUTINES

This section lists the routines related to **npix2nside** .

<code>idl</code>	version 6.1 or more is necessary to run <code>npix2nside</code> .
<code>nside2npix</code>	computes <code>Npix</code> corresponding to <code>Nside</code>
<code>pix2xxx</code> , <code>ang2xxx</code> , <code>vec2xxx</code> , ...	conversion between vector or angles and pixel index and vice-versa

<code>vec2pix, pix2vec</code>	conversion between vector and pixel index
<code>nest2ring, ring2nest</code>	conversion between NESTED and RING indices

EXAMPLE:

```
Nside = npix2nside(49152, ERROR=error)
```

Nside will be 64 because 49152 is a valid pixel number ($=12 \cdot 64^2$ and 64 is a power of 2), and error will be 0

EXAMPLE:

```
Nside = npix2nside(49151, ERROR=error)
```

Nside will be -1 and error: 1, because 49151 is not a valid number of **HEALPix** pixels over the full sky.

nside2npix

Location in HEALPix directory tree: `src/idl/toolkit/nside2npix.pro`

This IDL facility provides the number of pixels N_{pix} over the full sky corresponding to resolution parameter N_{side} .

FORMAT IDL> $N_{\text{pix}} = \text{NSIDE2NPIX}$ (N_{side} [,ERROR=])

QUALIFIERS

N_{side}	HEALPix resolution parameter (scalar integer), should be a valid N_{side} (power of 2 $\leq 2^{29}$)
N_{pix}	number of pixels, $N_{\text{pix}} = 12 * N_{\text{side}}^2$ if N_{side} is a valid resolution parameter or -1 otherwise

KEYWORDS

ERROR =	error flag, set to 1 on output if N_{side} is NOT valid, or stays to 0 otherwise.
---------	--

DESCRIPTION nside2npix checks that the given N_{side} is valid (power of 2 in $\{1, \dots, 2^{29}\}$) and then computes the corresponding number of pixels $N_{\text{pix}} = 12 N_{\text{side}}^2$.

RELATED ROUTINES

This section lists the routines related to **nside2npix**.

idl	version 6.1 or more is necessary to run nside2npix
npix2nside	computes N_{side} corresponding to N_{pix}
pix2xxx , ang2xxx , vec2xxx , ...	conversion between vector or angles and pixel index and vice-versa
vec2pix , pix2vec	conversion between vector and pixel index

`nest2ring, ring2nest` conversion between NESTED and RING indices

EXAMPLE:

```
Npix = nside2npix(256, ERROR=error)
```

Npix will be 786432 the number of pixels over the full sky for the **HEALPix** resolution parameter 256 and error will be 0

EXAMPLE:

```
Npix = nside2npix(248, ERROR=error)
```

Npix will be -1 and error: 1, because 248 is not a valid value for a **HEALPix** resolution parameter

nside2ntemplates

Location in HEALPix directory tree: `src/idl/toolkit/nside2ntemplates.pro`

This IDL facility provides the number of template pixels `Ntemplates` corresponding to resolution parameter `Nside`. Each template pixel has a different shape that *can not* be matched (by rotation or reflexion) to that of any of the other templates.

FORMAT IDL> `Ntemplates=NSIDE2NTEMPLATES`
`(Nside [,ERROR=])`

QUALIFIERS

<code>Nside</code>	HEALPix resolution parameter (scalar integer), should be a valid <code>Nside</code> (power of 2 in $\{1, \dots, 8192\}$)
<code>Ntemplates</code>	number of templates

KEYWORDS

<code>ERROR =</code>	error flag, set to 1 on output if <code>Nside</code> is NOT valid, or stays to 0 otherwise.
----------------------	---

DESCRIPTION `nside2ntemplates` outputs the number of template pixels

$$N_{\text{template}} = \frac{1 + N_{\text{side}}(N_{\text{side}} + 6)}{4}.$$

If the argument N_{side} is not valid, a warning is issued and the error flag is raised.

RELATED ROUTINES

This section lists the routines related to **`nside2ntemplates`**.

<code>idl</code>	version 6.1 or more is necessary to run <code>nside2ntemplates</code> .
------------------	---

<code>template_pixel_ring</code>	
<code>template_pixel_nest</code>	return the template pixel associated with any HEALPix pixel
<code>same_shape_pixels_ring</code>	
<code>same_shape_pixels_nest</code>	return the ordered list of pixels having the same shape as a given pixel template

EXAMPLE:

```
Ntemplates = nside2ntemplates(256, ERROR=error)
```

Ntemplates will be 16768 the number of template pixels for the **HEALPix** resolution parameter 256 and error will be 0

orthcursor

Location in HEALPix directory tree: `src/idl/visu/orthcursor.pro`

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a orthographic projection of a **HEALPix** map.

FORMAT IDL> ORTHCURSOR, [cursor_type=,
 file_out=]

QUALIFIERS

see [mollcursor](#)

DESCRIPTION orthcursor should be called immediately after orthview. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by orthview. For more details, or in case of problems under **Mac OS X**, see [mollcursor](#).

RELATED ROUTINES

This section lists the routines related to **orthcursor**.

see [mollcursor](#)

EXAMPLE:

`orthcursor`

After orthview has read in a map and generated its orthographic projection, orthcursor is run to determine the position and flux of bright synchrotron sources, for example.

orthview

Location in HEALPix directory tree: `src/idl/visu/orthview.pro`

This IDL facility provides a means to visualise a full sky or half sky orthographic projection (projection onto a tangent plane from a point located at infinity) of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

FORMAT

```
IDL> ORTHVIEW, File, [ Select, ] [ /ASINH,
CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP,
EXECUTE=, FACTOR=, FITS=, /FLIP, GAL_CUT=,
GIF=, GLSIZE=, GRATICULE=, /HALF_SKY, HBOUND=,
/HELP, /HIST_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-
ULE=, JPEG=, /LOG, MAP_OUT=, MAX=, MIN=,
/NESTED, /NO_DIPOLE, /NO_MONOPOLE, /NOBAR,
/NOLABELS, /NOPOSITION, OFFSET=, OUTLINE=,
PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZ=,
PYSIZ=, RESO_ARCMIN=, RETAIN=, ROT=, /SAVE,
/SHADED, /SILENT, STAGGER=, SUBTITLE=, TITLE-
PLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=,
WINDOW=, XPOS=, YPOS=]
```

QUALIFIERS

For a full list of qualifiers see [mollview](#)

KEYWORDS

For a full list of keywords see [mollview](#)

DESCRIPTION `orthview` reads in a **HEALPix** sky map in FITS format and generates an orthographic projection of it, that can be visualized on the screen or exported in a GIF, PNG, Postscript or FITS file. `orthview` allows the selection of the coordinate system, point of projection, map size, color table, color bar inclusion, linear or log scaling, histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc.* It also allows the representation of the polarization field.

RELATED ROUTINES

This section lists the routines related to **orthview**.

see [mollview](#)

EXAMPLE:

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
orthview,map,/online,graticule=[45,30],rot=[10,20,30],$
    title='Orthographic projection',subtitle='orthview' $
    outline=triangle
```

makes an orthographic projection of map (see Figure 1d on page 109) after an arbitrary rotation, with a graticule grid (with a 45° step in longitude and 30° in latitude) and an arbitrary triangular outline

pix2xxx, ang2xxx, vec2xxx, nest2ring, ring2nest

Location in HEALPix directory tree: **src/idl/toolkit/**

These routines provide conversion between pixel number in the **HEALPix** map and (θ, ϕ) or (x, y, z) coordinates on the sphere. Some of these routines are listed here.

QUALIFIERS

name (dim.)	type	in/out	description
nside	scalar integer	IN	N_{side} parameter for the HEALPix map.
ipnest(n)	vector integer	—	pixel identification number in NESTED scheme over the range $\{0, N_{\text{pix}} - 1\}$.
ipring(n)	vector integer	—	pixel identification number in RING scheme over the range $\{0, N_{\text{pix}} - 1\}$.
theta(n)	vector double	—	colatitude in radians measured southward from north pole in $\{0, \pi\}$
phi(n)	vector double	—	longitude in radians, measured eastward in $\{0, 2\pi\}$.
vector(n,3)	array double	—	three dimensional cartesian position vector (x, y, z) . The north pole is $(0, 0, 1)$. An output vector is normalised to unity. The coordinates are ordered as follows $x(0), \dots, x(n-1)$, $y(0), \dots, y(n-1)$, $z(0), \dots, z(n-1)$
vertex(n,3,4)	array double	optional OUT	three dimensional cartesian position vector (x, y, z) . Contains the location of the four vertices (=corners) of a pixel in the order North, West, South, East. The coordinates are ordered as follows $x_N(0), \dots, x_N(n-1)$, $y_N(0), \dots, y_N(n-1)$, $z_N(0), \dots, z_N(n-1)$, $x_W(0), \dots, x_W(n-1)$, $y_W(0), \dots, y_W(n-1)$, $z_W(0), \dots, z_W(n-1)$, and so on with South and East vertices

ROUTINES:**pix2ang_ring, nside, ipring, theta, phi**

renders *theta* and *phi* coordinates of the nominal pixel center given the pixel number *ipring* and a map resolution parameter *nside*.

pix2vec_ring, nside, ipring, vector [,vertex]

renders cartesian vector coordinates of the nominal pixel center given the pixel number *ipring* and a map resolution parameter *nside*. Optionally returns the location of the 4 vertices for the pixel(s) under consideration

ang2pix_ring, nside, theta, phi, ipring

renders the pixel number *ipring* for a pixel which, given the map resolution parameter *nside*, contains the point on the sphere at angular coordinates *theta* and *phi*.

vec2pix_ring, nside, vector, ipring

renders the pixel number *ipring* for a pixel which, given the map resolution parameter *nside*, contains the point on the sphere at cartesian coordinates *vector*.

pix2ang_nest, nside, ipnest, theta, phi

renders *theta* and *phi* coordinates of the nominal pixel center given the pixel number *ipnest* and a map resolution parameter *nside*.

pix2vec_nest, nside, ipnest, vector [,vertex]

renders cartesian vector coordinates of the nominal pixel center given the pixel number *ipnest* and a map resolution parameter *nside*. Optionally returns the location of the 4 vertices for the pixel(s) under consideration

ang2pix_nest, nside, theta, phi, ipnest

renders the pixel number *ipnest* for a pixel which, given the map resolution parameter *nside*, contains the point on the sphere at angular coordinates *theta* and *phi*.

vec2pix_nest, nside, vector, ipnest

renders the pixel number *ipnest* for a pixel which, given the map resolution parameter *nside*, contains the point on the sphere at cartesian coordinates *vector*.

nest2ring, nside, ipnest, ipring

performs conversion from NESTED to RING pixel number.

ring2nest, nside, ipring, ipnest

performs conversion from RING to NESTED pixel number.

RELATED ROUTINES

This section lists the routines related to **pix2xxx**, **ang2xxx**, **vec2xxx**, **nest2ring**, **ring2nest**.

	idl	version 6.1 or more is necessary to run pix2xxx, ang2xxx,... .
	npix2nside	computes N_{side} (resolution) corresponding to N_{pix} (total pixel number)
	nside2npix	computes N_{pix} corresponding to N_{side}
	ang2vec, vec2ang	geometrical conversion between position angles and position vector

EXAMPLE:

```
pix2ang_ring, 256, [17,1000], theta, phi
print,theta,phi
```

```
returns
0.0095683558      0.070182078
2.8797933         5.4620872
position of 2 pixels 17 and 1000 in the RING scheme with
parameter 256.
```

query_disc

Location in HEALPix directory tree: `src/idl/toolkit/query_disc.pro`

This IDL facility provides a means to find the index of all pixels within an angular distance `Radius` from a defined center.

FORMAT IDL> query_disc , `Nside`, `Vector0`, `Radius`, `Listpix`, [`Nlist`, `/DEG`, `/NESTED`, `/INCLUSIVE`]

QUALIFIERS

<code>Nside</code>	HEALPix resolution parameter used to index the pixel list (scalar integer)
<code>Vector0</code>	position vector of the disc center (3 elements vector) NB : the norm of <code>Vector0</code> does not have to be one, what is consider is the intersection of the sphere with the line of direction <code>Vector0</code> .
<code>Radius</code>	radius of the disc (in radians, unless <code>DEG</code> is set), (scalar real)
<code>Listpix</code>	on output: list of ordered index for the pixels found within a radius <code>Radius</code> of the position defined by <code>vector0</code> . The RING numbering scheme is used unless the keyword <code>NESTED</code> is set. (= -1 if the radius is too small and no pixel is found)
<code>Nlist</code>	on output: number of pixels in <code>Listpix</code> (=0 if no pixel is found).

KEYWORDS

<code>/DEG</code>	if set <code>Radius</code> is in degrees instead of radians
<code>/NESTED</code>	if set, the output list uses the NESTED numbering scheme instead of the default RING
<code>/INCLUSIVE</code>	if set, all the pixels overlapping (even partially) with the disc are listed, otherwise only those whose center lies within the disc are listed

DESCRIPTION query_disc finds the pixels within the given disc in a selective way WITHOUT scanning all the sky pixels. The numbering scheme of the output list and the inclusiveness of the disc can be changed

RELATED ROUTINES

This section lists the routines related to **query_disc** .

idl	version 6.1 or more is necessary to run query_disc .
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon, query_strip, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle

EXAMPLE:

```
query_disc , 256L, [.5,.5,0.], 10., listpix, nlist, /Deg, /Nest
```

On return listpix contains the index of the (5982) pixels within 10 degrees from the point on the sphere having the direction [.5,.5,0.]. The pixel indices correspond to the Nested scheme with resolution 256.

query_polygon

Location in HEALPix directory tree: `src/idl/toolkit/query_polygon.pro`

This IDL facility provides a means to find the index of all pixels belonging to a spherical polygon defined by its vertices

FORMAT IDL> query_polygon , Nside, Vlist, Listpix,
[Nlist, HELP=, NESTED=, INCLUSIVE=]

QUALIFIERS

Nside	HEALPix resolution parameter used to index the pixel list (scalar integer)
Vlist	3D cartesian position vector of the polygon vertices. Array of dimension (n,3) where n is the number of vertices
Listpix	on output: list of ordered index for the pixels found in the polygon. The RING numbering scheme is used unless the keyword NESTED is set. (= -1 if the polygon is too small and no pixel is found)
Nlist	on output: number of pixels in Listpix (=0 if no pixel is found).

KEYWORDS

HELP=	if set, the documentation header is printed out and the routine exits
NESTED =	if set, the output list uses the NESTED numbering scheme instead of the default RING
INCLUSIVE =	if set, all the pixels overlapping (even partially) with the polygon are listed, otherwise only those whose center lies within the polygon are listed

DESCRIPTION query_polygon finds the pixels within the given polygon in a selective way WITHOUT scanning all the sky pixels. The polygon should be convex, or have only one concave vertex. The edges should not intersect each other. The numbering scheme of the output list and the inclusiveness of the polygon can be changed

RELATED ROUTINES

This section lists the routines related to **query_polygon** .

idl	version 6.1 or more is necessary to run query_polygon .
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon, query_strip, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle

EXAMPLE:

```
query_polygon , 256L, [[0,1,1,0],[0,0,1,1],[1,0,-1,0]], listpix, nlist
```

On return listpix contains the index of the (131191) pixels contained in the polygon with vertices of cartesian coordinates (0,0,1), (1,0,0), (1,1,-1) and (0,1,0). The pixel indices correspond to the RING scheme with resolution 256.

query_strip

Location in HEALPix directory tree: `src/idl/toolkit/query_strip.pro`

This IDL facility provides a means to find the index of all pixels belonging to a latitude strip defined by its bounds

FORMAT IDL> query_strip , Nside, Theta1, Theta2,
Listpix, [Nlist, NESTED=, INCLUSIVE=,
HELP=]

QUALIFIERS

Nside	HEALPix resolution parameter used to index the pixel list (scalar integer)
Theta1	colatitude lower bound in radians measured from North Pole (between 0 and π).
Theta2	colatitude upper bound in radians measured from North Pole (between 0 and π). If <code>theta1 < theta2</code> , the pixels lying in <code>[theta1, theta2]</code> are output, otherwise, the pixel lying in <code>[0, theta2]</code> and those lying in <code>[theta1, π]</code> are output.
Listpix	on output: list of ordered index for the pixels found in the strip. The RING numbering scheme is used unless the keyword NESTED is set. (<code>=-1</code> if the strip is too small and no pixel is found)
Nlist	on output: number of pixels in Listpix (<code>=0</code> if no pixel is found).

KEYWORDS

NESTED =	if set, the output list uses the NESTED numbering scheme instead of the default RING
INCLUSIVE =	if set, all the pixels overlapping (even partially) with the strip are listed, otherwise only those whose center lies within the strip are listed

/HELP	if set, the routine prints its documentation header and exits.
-------	--

DESCRIPTION query_strip finds the pixels within the given strip in a selective way WITHOUT scanning all the sky pixels. The numbering scheme of the output list and the inclusiveness of the strip can be changed

RELATED ROUTINES

This section lists the routines related to **query_strip** .

idl	version 6.1 or more is necessary to run query_strip .
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon and triangle

EXAMPLE:

```
query_strip , 256, 0.75*!PI, !PI/5, listpix, nlist, /nest
```

Returns the NESTED pixel index of all pixels with colatitude in $[0, \pi/5]$ and those with colatitude in $[3\pi/4, \pi]$

query_triangle

Location in HEALPix directory tree: `src/idl/toolkit/query_triangle.pro`

This IDL facility provides a means to find the index of all pixels belonging to a spherical triangle defined by its vertices

FORMAT IDL> query_triangle , Nside, Vector1, Vector2, Vector3, Listpix, [Nlist, NESTED=, INCLUSIVE=]

QUALIFIERS

Nside	HEALPix resolution parameter used to index the pixel list (scalar integer)
Vector1	3D cartesian position vector of the triangle first vertex
Vector2	3D cartesian position vector of the triangle second vertex
Vector3	3D cartesian position vector of the triangle third vertex NB : the norm of Vector* does not have to be one, what is considered is the intersection of the sphere with the line of direction Vector*.
Listpix	on output: list of ordered index for the pixels found in the triangle. The RING numbering scheme is used unless the keyword NESTED is set. (= -1 if the triangle is too small and no pixel is found)
Nlist	on output: number of pixels in Listpix (=0 if no pixel is found).

KEYWORDS

NESTED =	if set, the output list uses the NESTED numbering scheme instead of the default RING
INCLUSIVE =	if set, all the pixels overlapping (even partially) with the triangle are listed, otherwise only those whose center lies within the triangle are listed

DESCRIPTION query_triangle finds the pixels within the given triangle in a selective way WITHOUT scanning all the sky pixels. The numbering scheme of the output list and the inclusiveness of the triangle can be changed

RELATED ROUTINES

This section lists the routines related to **query_triangle** .

idl	version 6.1 or more is necessary to run query_triangle .
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon, query_strip, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle

EXAMPLE:

```
query_triangle , 256L, [1,0,0],[0,1,0],[0,0,1], listpix, nlist
```

On return listpix contains the index of the (98560) pixels lying in the octant ($x > 0, y > 0, z > 0$). The pixel indices correspond to the RING scheme with resolution 256.

read_fits_cut4

Location in HEALPix directory tree: `src/idl/fits/read_fits_cut4.pro`

This IDL facility reads a cut sky **HEALPix** map from a FITS file according to the **HEALPix** convention. The format used for the FITS file follows the one used for Boomerang98 and is adapted from COBE/DMR. This routine can also be used to read polarized cut sky map, where each Stokes parameter is stored in a different extension of the same FITS file.

FORMAT IDL> READ_FITS_CUT4 , File, Pixel, Signal [, N_Obs, Serror, EXTENSION=, HDR=, XHDR=, NSIDE=, ORDERING=, COORDSYS=]

QUALIFIERS

File	name of a FITS file in which the map is to be written
Pixel	(OUT, LONG vector), index of observed (or valid) pixels
Signal	(OUT, FLOAT vector), value of signal in each observed pixel
N_Obs	(OUT, LONG or INT vector, Optional), number of observation per pixel
Serror	(OUT, FLOAT vector, Optional), <i>rms</i> of signal in pixel. For white noise, this is $\propto 1/\sqrt{n_obs}$

KEYWORDS

EXTENSION = (IN, optional),
0 based number of extension to read. Extension 0 contains the temperature information, while extensions 1 and 2 contain respectively the Q and U Stokes parameters related information.
(**default:** 0)

HDR =	(OUT, optional), String array containing the primary header.
XHDR =	(OUT, optional), String array containing the extension header.
NSIDE=	(OUT, optional), returns on output the HEALPix resolution parameter, as read from the FITS header. Set to -1 if not found
ORDERING=	(OUT, optional), returns on output the pixel ordering, as read from the FITS header. Either 'RING' or 'NESTED' or ' ' (if not found).
COORDSYS=	(OUT, optional), returns on output the astrophysical coordinate system used, as read from FITS header (value of keywords COORDSYS or SKYCOORD)

DESCRIPTION

RELATED ROUTINES

This section lists the routines related to **read_fits_cut4** .

idl	version 6.1 or more is necessary to run read_fits_cut4
write_fits_cut4	This HEALPix IDL facility can be used to generate the FITS format <i>cut-sky</i> maps compliant with HEALPix convention and readable by read_fits_cut4 .
read_fits_cut4 , read_fits_map read_tqu , read_fits_s	HEALPix IDL routines to read cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets from FITS files
sxpar	This IDL routine (included in HEALPix package) can be used to extract FITS keywords from the header(s) HDR or XHDR read with read_fits_cut4 .

read_fits_map

Location in HEALPix directory tree: `src/idl/fits/read_fits_map.pro`

This IDL facility reads in a **HEALPix** map from a FITS file.

FORMAT IDL> READ_FITS_MAP , File, T_sky, [Hdr, Exthdr, PIXEL=, SILENT=, NSIDE=, ORDERING=, COORDSYS=, EXTENSION=, HELP=]

QUALIFIERS

File	name of a FITS file containing the HEALPix map in an extension or in the image field
T_sky	variable containing on output the HEALPix map
Hdr	(optional), string variable containing on output the FITS primary header
Exthdr	(optional), string variable containing on output the FITS extension header
PIXEL=	(optional), pixel number to read from or pixel range to read (in the order of appearance in the file), starting from 0. if ≥ 0 scalar : read from pixel to the end of the file if two elements array : reads from pixel[0] to pixel[1] (included) if absent : read the whole file
NSIDE=	(optional), returns on output the HEALPix resolution parameter, as read from the FITS header. Set to -1 if not found
ORDERING=	(optional), returns on output the pixel ordering, as read from

the FITS header. Either 'RING' or 'NESTED' or ' ' (if not found).

COORDSYS= (optional),
returns on output the astrophysical coordinate system used, as read from FITS header (value of keywords COORDSYS or SKYCOORD)

Extension= (optional),
extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension *after* primary array) or the case-insensitive value of its EXTNAME keyword. If absent, all available extensions are read.

KEYWORDS

HELP= if set, an extensive help is displayed and no file is read

SILENT= if set, no message is issued during normal execution

DESCRIPTION read_fits_map reads in a **HEALPix** sky map from a FITS file, and outputs the variable `T_sky`, where the optional variables `Hdr` and `Exthdr` contain respectively the primary and extension headers. According to **HEALPix** convention, the map should be stored as a FITS file binary table extension. Note: the routine `read_tqu` which requires less memory is recommended when reading *large polarized* maps.

RELATED ROUTINES

This section lists the routines related to `read_fits_map`.

idl version 6.1 or more is necessary to run read_fits_map

`read_fits_cut4`, `read_fits_map`
`read_tqu`, `read_fits_s` **HEALPix** IDL routines to read cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets from FITS files

sxpar	This IDL routine (included in HEALPix package) can be used to extract FITS keywords from the header(s) <code>Hdr</code> or <code>Xhdr</code> read with <code>read_fits_map</code> .
synfast	This HEALPix facility will generate the FITS format sky map that can be read by <code>read_fits_map</code> .
<code>write_fits_map</code>	This HEALPix IDL facility can be used to generate the FITS format sky maps compliant with HEALPix convention and readable by <code>read_fits_map</code> .

EXAMPLE:

```
read_fits_map, 'planck100GHZ-LFI.fits', map, hdr, xhdr, /silent
```

`read_fits_map` reads in the file 'planck100GHZ-LFI.fits' and outputs the **HEALPix** map in `map`, the primary header in `hdr` and the extension header in `xhdr`.

read_fits_s

Location in HEALPix directory tree: `src/idl/fits/read_fits_s.pro`

This IDL facility reads a FITS file into an IDL structure.

FORMAT IDL> READ_FITS_S , File, Prim_stc,
[Xten_stc, COLUMNS=, EXTENSION=,
/HELP, /MERGE]

QUALIFIERS

File	name of a FITS file containing the healpix map(s) in an extension or in the image field
Prim_stc	variable containing on output an IDL structure with the following fields: - primary header (tag : 0, tag name : HDR) - primary image (if any, tag : 1, tag name : IMG)
Xten_stc	(optional), variable containing on output an IDL structure with the following fields: - extension header (tag : 0, tag name : HDR) - data column 1 (if any, tag : 1, tag name given by TTYPE1 (with all spaces removed and only letters, digits and underscore) - data column 2 (if any, tag : 2, tag name given by TTYPE2) ...
Columns=	(optional), list of columns to be read from a binary table can be a list of integer (1 based) indexing the columns positions or a list of names matching the TTYPE* of the columns by default, all columns are read
Extension=	(optional), extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension <i>after</i> primary array) or the case-insensitive value of its EXTNAME keyword. (default: 0)

KEYWORDS

/HELP	if set, an extensive help is displayed and no file is read
/MERGE	if set Prim_stc contains : - the concatenated primary and extension header (tag name : HDR) - primary image (if any, tag name : IMG) - data column 1 ... and Exten_stc is set to 0 (default: :) not set (or set to 0)

DESCRIPTION `read_fits_s` reads in any type of FITS file (Image, Binary table or Ascii table) and outputs the data in IDL structures

RELATED ROUTINES

This section lists the routines related to **read_fits_s** .

idl	version 6.1 or more is necessary to run <code>read_fits_s</code>
synfast	This HEALPix facility will generate the FITS format sky map that can be read by <code>read_fits_s</code> .
<code>read_fits_cut4</code> , <code>read_fits_map</code> <code>read_tqu</code> , <code>read_fits_s</code>	HEALPix IDL routines to read cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets from FITS files
<code>write_fits_sb</code>	This HEALPix IDL facility can be used to generate FITS format sky maps readable by <code>read_fits_s</code> .

EXAMPLE:

```
read_fits_s , 'dmr_skymap_90a_4yr.fits', pdata, xdata
```

`read_fits_s` reads in the file 'dmr_skymap_90a_4yr.fits'. On output, `pdata` contains the primary header and `xdata` is a structure whose first field is the extension header, and the other fields are vectors with respective tag names PIXEL, SIGNAL, N_OBS, ERROR, ... (see `help,/struc,xdata`)

read_tqu

Location in HEALPix directory tree: `src/idl/fits/read_tqu.pro`

This IDL facility reads a temperature+polarization Healpix map (T,Q,U) from a binary table FITS file, with optionally the error (dT,dQ,dU) and correlation (dQU, dTU, dTQ) from separate extensions

FORMAT IDL> READ_TQU , File, TQU, [Extension=, Hdr=, Xhdr=, /HELP, Nside=, Ordering=, Coordsys=]

QUALIFIERS

File	name of a FITS file from which the maps are to be read
TQU	: array of Healpix maps of size $(N_{\text{pix}}, 3, \text{n_ext})$ where N_{pix} is the total number of Healpix pixels on the sky, and $\text{n_ext} \leq 3$ is the number of extensions read Three maps are available in each extension of the FITS file : -the temperature+polarization Stokes parameters maps (T,Q,U) in extension 0 -the error maps (dT,dQ,dU) in extension 1 (if applicable) -the correlation maps (dQU, dTU, dTQ) in extension 2 (if applicable)
Extension=	(optional), extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension <i>after</i> primary array) or the case-insensitive value of its EXTNAME keyword. If absent, all available extensions are read.
Hdr=	(optional), string variable containing on output the contents of the primary header. (If already present, FITS reserved keywords will be automatically updated).

Xhdr=	(optional), string variable containing on output the contents of the extension header. If several extensions are read, then the extension headers are returned ap- pended into one string array.
Nside=	(optional), returns on output the HEALPix resolution pa- rameter, as read from the FITS header. Set to -1 if not found
Ordering=	(optional), returns on output the pixel ordering, as read from the FITS header. Either 'RING' or 'NESTED' or ' ' (if not found).
Coordsys=	(optional), returns on output the astrophysical coordinate system used, as read from FITS header (value of keywords COORDSYS or SKYCOORD)

KEYWORDS

/HELP	if set, an extensive help is displayed and no file is read
-------	---

DESCRIPTION `read_tqu` reads out Stokes parameters (T,Q,U) maps for the whole sky into a FITS file. It is also possible to read the error per pixel for each map and the correlation between fields, as subsequent extensions of the same FITS file (see qualifiers above). Therefore the file may have up to three extensions with three maps in each. Extensions can be written together or one by one (in their physical order) using the Extension option

RELATED ROUTINES

This section lists the routines related to **read_tqu**.

idl	version 6.1 or more is necessary to run <code>read_tqu</code>
synfast	This HEALPix f90 facility can be used to generate temperature+polarization maps that can be read with <code>read_tqu</code>

<code>write_tqu</code>	This HEALPix IDL facility can be used to write out temperature+polarization that can be read by <code>read_tqu</code> .
<code>read_fits_cut4</code> , <code>read_fits_map</code> <code>read_tqu</code> , <code>read_fits_s</code>	HEALPix IDL routines to read cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets from FITS files
<code>read_fits_s</code>	This general purpose HEALPix IDL facility can be used to read into an IDL structure maps contained in binary table FITS files.
<code>sxpar</code>	This IDL routine (included in HEALPix package) can be used to extract FITS keywords from the header(s) HDR or XHDR read with <code>read_tqu</code> .

EXAMPLE:

```
read_tqu, 'map_polarization.fits', TQU, xhdr=xhdr
```

Reads into `TQU` the polarization maps contained in the FITS file 'map_polarization.fits'. The variable `xhdr` will contain the extension(s) header.

remove_dipole

Location in HEALPix directory tree: `src/idl/misc/remove_dipole.pro`

This IDL facility provides a means to fit and remove the dipole and monopole from a **HEALPix** map.

FORMAT IDL> REMOVE_DIPOLE, Map [, Weight, BAD_DATA=, GAL_CUT=, COORD_IN=, COORD_OUT=, Covariance_Matrix=, Dipole=, Monopole=, /NOREMOVE, NSIDE=, /ONLYMONOPOLE, ORDERING=, PIXEL=, /SILENT, UNITS=, /HELP]

QUALIFIERS

Map	input and output, vector map from which monopole and dipole are to be removed (also used for output). Assumed to be a full sky data set, unless PIXEL is set and has the same size as map
Weight	input, vector, optional same size as map, describe weighting scheme to apply to each pixel for the fit (default: uniform weight)
BAD_DATA =	scalar float, value given on input to bad pixels (default: <code>!healpix.bad_value</code> $\equiv -1.6375 \times 10^{30}$).
GAL_CUT=	if set to a value larger than 0, the pixels with galactic latitude $ b < \text{gal_cut}$ degrees are not considered in the fit. NB: the cut is <i>really</i> done in Galactic coordinates. If the input coordinates are different (see <code>Coord_In</code>), the map is rotated into galactic before applying the cut.
COORD_IN =	string, map coordinate system (either 'Q' or 'C': equatorial, 'G': galactic or 'E': ecliptic; upper/lower case accepted)

	(default: 'G' (galactic))
COORD_OUT =	string, coordinate system (see above) in which to output dipole vector in variable Dipole (default: same as coord_in)
Covariance_Matrix =	OUTPUT, scalar (or symmetric 4x4 matrix), covariance of the statistical errors made on monopole (and dipole) determination
Dipole=	OUTPUT, 3d vector, coordinates of best fit dipole (done simultaneously with monopole), same units as input map
Monopole=	OUTPUT, scalar float, value found for the best fit monopole (done simultaneously with dipole), same units as input map
NSIDE=	scalar integer, healpix resolution parameter
ORDERING=	string, ordering scheme (either 'RING' or 'NESTED')
PIXEL=	input, vector, gives the Healpix index of the pixels whose temperature is actually given in map (for cut sky maps). If present, must match Map in size. If absent, it is assumed that the map covers the whole sky.
UNITS=	string, units of the input map

KEYWORDS

/NOREMOVE	if set, the best fit dipole and monopole are computed but not removed (ie, Map is unchanged)
/ONLYMONOPOLE	if set, fit (and remove) only the monopole
/HELP	if set, only display documentation header
/SILENT	if set, the routine works silently

DESCRIPTION remove_dipole makes a simultaneous least square fit of the monopole and dipole on all the valid pixels of Map (those with a value different from BAD_DATA) with a galactic latitude larger in magnitude than GAL_CUT (in degrees). The position of the pixels on the sky is reconstructed from NSIDE and ORDERING. If Map does not cover the full sky, the actual indices of the concerned pixels should be given in PIXEL

RELATED ROUTINES

This section lists the routines related to **remove_dipole**.

idl	version 6.1 or more is necessary to run remove_dipole.
-----	--

reorder

Location in HEALPix directory tree: `src/idl/toolkit/reorder.pro`

This IDL facility allows the reordering of a full sky map from NESTED to RING scheme and vice-versa.

FORMAT IDL> **Result** = REORDER (**Input_map** [,
 /**HELP**, **In**=, **Out**=, /**N2R**, /**R2N**])

QUALIFIERS

Result	variable containing on output the reordered map
Input_map	variable containing the input map

KEYWORDS

/HELP	if set, the documentation header is printed out and the code exits
In=	specifies the input ordering, can be either 'RING' or 'NESTED'
Out=	specifies the output ordering, can be either 'RING' or 'NESTED'
/N2R	If set, does the NESTED to RING conversion, equivalent to In='NESTED' and Out='RING'
/R2N	If set, does the RING to NESTED conversion, equivalent to In='RING' and Out='NESTED'

DESCRIPTION reorder allows the reordering of a full sky map from NESTED to RING scheme and vice-versa

RELATED ROUTINES

This section lists the routines related to **reorder** .

idl	version 6.1 or more is necessary to run reorder
-----	---

`ud_grade` downgrades or upgrades a full-sky or cut-sky **HEALPix** map.

EXAMPLE:

```
map_nest = reorder(map_ring, in='ring', out='nest')
```

The RING ordered map `map_ring` is converted to the NESTED map `map_nest`.

rotate_coord

Location in HEALPix directory tree: `src/idl/misc/rotate_coord.pro`

This IDL facility provides a means to rotate a set of 3D position vectors (and their Stokes parameters Q and U) between to astrophysical coordinate systems or by an arbitrary rotation.

FORMAT IDL> Outvec = ROTATE_COORD(Invec [, Inco=, Outco=, Euler_Matrix=, Stokes_Parameters=])

QUALIFIERS

Invec	input, array of size (n,3) : set of 3D position vectors
Outvec	output, array of size (n,3) : rotated 3D vectors
Inco=	input, character string (either 'Q' or 'C': equatorial, 'G': galactic or 'E': ecliptic) describing the input coordinate system
Outco=	input, character string (see above) describing the output coordinate system. Can not be used together with Euler_Matrix
Euler_Matrix=	input, array of size (3,3). Euler Matrix describing the rotation to apply to vectors. (default: unity : no rotation). Can not be used together with a change in coordinates.
Stokes_Parameters=	input and output, array of size (n, 2) : values of the Q and U Stokes parameters on the sphere for each of the input position vector. Q and U are defined wrt the local parallel and meridian and are therefore transformed in a non trivial way in case of rotation

DESCRIPTION `rotate_coord` is a generalisation of the Astro library routine `skyconv`. It allows a rotation of 3D position vectors between two standard astronomic coordinates system but also an arbitrary rotation described by its Euler Matrix. It can also be applied to compute the effect of a rotation on the linear polarization Stokes parameters (Q and U) expressed in local coordinates system at the location of each of the input 3D vectors.

RELATED ROUTINES

This section lists the routines related to **`rotate_coord`**.

idl	version 6.1 or more is necessary to run <code>rotate_coord</code> .
<code>euler_matrix_new</code>	constructs the Euler Matrix for a set of three angles and three axes of rotation

same_shape_pixels_XXXX

Location in HEALPix directory tree: `src/idl/toolkit/same_shape_pixels_nest.pro`,
`src/idl/toolkit/same_shape_pixels_ring.pro`

These IDL facilities provide the ordered list of all **HEALPix** pixels having the same shape as a given template, for a resolution parameter N_{side} .

FORMAT IDL> same_shape_pixels_nest, Nside, Template, List_Pixels_Nest [, Reflexion, NREPLICATIONS=]

FORMAT IDL> same_shape_pixels_ring, Nside, Template, List_Pixels_Ring [, Reflexion, NREPLICATIONS=]

QUALIFIERS

Nside	(IN, scalar) the HEALPix N_{side} parameter.
Template	(IN, scalar) identification number of the template (this number is independent of the numbering scheme considered).
List_Pixel_Nest	(OUT, vector) ordered list of NESTED scheme identification numbers for all pixels having the same shape as the template provided
List_Pixel_Ring	(OUT, vector) ordered list of RING scheme identification numbers for all pixels having the same shape as the template provided
Reflexion	(OUT, OPTIONAL, vector) in $\{0, 3\}$ encodes the transformation(s) to apply to each of the returned pixels to match exactly in shape and position the template provided. 0: rotation around the polar axis only, 1: rotation + East-West swap (ie, reflexion around meridian), 2: rotation + North-South swap (ie, reflexion around Equator), 3: rotation + East-West and North-South swaps

KEYWORDS

NREPLICATIONS (OUT, OPTIONAL, scalar) number of pixels having the same shape as the template. It is also the length of the vectors `List_Pixel_Nest`, `List_Pixel_Ring` and `Reflexion`. It is either 8, 16, $4N_{\text{side}}$ or $8N_{\text{side}}$.

DESCRIPTION `same_shape_pixels_XXXX` provide the ordered list of all **HEALPix** pixels having the same shape as a given template, for a resolution parameter N_{side} . Depending on the template considered the number of such pixels is either 8, 16, $4N_{\text{side}}$ or $8N_{\text{side}}$. The template pixels are all located in the Northern Hemisphere, or on the Equator. They are chosen to have their center located at

$$z = \cos(\theta) \geq 2/3, \quad 0 < \phi \leq \pi/2, \\ 2/3 > z \geq 0, \quad \phi = 0, \quad \text{or} \quad \phi = \frac{\pi}{4N_{\text{side}}}.$$

They are numbered continuously from 0, starting at the North Pole, with the index increasing in ϕ , and then increasing for decreasing z .

EXAMPLE:

`same_shape_pixels_ring, 256, 1234, list_pixels, reflexion, nrep=np`

Returns in `list_pixels` the RING-scheme index of the all the pixels having the same shape as the template #1234 for $N_{\text{side}} = 256$. Upon return `reflexion` will contain the reflexions to apply to each pixel returned to match the template, and `np` will contain the number of pixels having that same shape (16 in that case).

RELATED ROUTINES

This section lists the routines related to **same_shape_pixels_XXXX**.

nside2templates returns the number of template pixel shapes avail-

	able for a given N_{side} .
<code>template_pixel_ring</code>	
<code>template_pixel_nest</code>	return the template shape matching the pixel provided

template_pixel_xxxx

Location in HEALPix directory tree: `src/idl/toolkit/template_pixel_nest.pro`,
`src/idl/toolkit/template_pixel_ring.pro`

These IDL facilities provide the index of the template pixel associated with a given **HEALPix** pixel, for a resolution parameter N_{side} .

FORMAT IDL> `template_pixel_nest`, `Nside`, `Pixel_Nest`,
`Template`, `Reflexion`

FORMAT IDL> `template_pixel_ring`, `Nside`, `Pixel_Ring`,
`Template`, `Reflexion`

QUALIFIERS

<code>Nside</code>	(IN, scalar) the HEALPix N_{side} parameter.
<code>Pixel_Nest</code>	(IN, scalar or vector) NESTED scheme pixel identification number(s) over the range $\{0, 12N_{\text{side}}^2 - 1\}$.
<code>Pixel_Ring</code>	(IN, scalar or vector) RING scheme pixel identification number(s) over the range $\{0, 12N_{\text{side}}^2 - 1\}$.
<code>Template</code>	(OUT, scalar or vector) identification number(s) of the template matching in shape the pixel(s) provided (the numbering scheme of the pixel templates is the same for both routines).
<code>Reflexion</code>	(OUT, scalar or vector) in $\{0, 3\}$ encodes the transformation(s) to apply to each pixel provided to match exactly in shape and position its respective template. 0: rotation around the polar axis only, 1: rotation + East-West swap (ie, reflexion around meridian), 2: rotation + North-South swap (ie, reflexion around Equator), 3: rotation + East-West and North-South swaps

DESCRIPTION `template_pixel_xxxx` provide the index of the template pixel associated with a given **HEALPix** pixel, for a resolution parameter N_{side} .

Any pixel can be *matched in shape* to a single of these templates by a combination of a rotation around the polar axis with reflexion(s) around a meridian and/or the equator.

The template pixels are all located in the Northern Hemisphere, or on the Equator. They are chosen to have their center located at

$$\begin{aligned} z = \cos(\theta) &\geq 2/3, & 0 < \phi &\leq \pi/2, \\ 2/3 > z &\geq 0, & \phi &= 0, \quad \text{or} \quad \phi = \frac{\pi}{4N_{\text{side}}}. \end{aligned}$$

They are numbered continuously from 0, starting at the North Pole, with the index increasing in ϕ , and then increasing for decreasing z .

EXAMPLE:

```
template_pixel_ring, 256, 500000, template, reflexion
```

Returns in `template` the index of the template pixel (16663) whose shape matches that of the pixel #500000 for $N_{\text{side}} = 256$. Upon return `reflexion` will contain 2, meaning that the template must be reflected around a meridian and around the equator (and then rotated around the polar axis) in order to match the pixel.

RELATED ROUTINES

This section lists the routines related to `template_pixel_xxxx`.

<code>nside2templates</code>	returns the number of template pixel shapes available for a given N_{side} .
<code>same_shape_pixels_ring</code>	
<code>same_shape_pixels_nest</code>	return the ordered list of pixels having the same shape as a given pixel template

ud_grade

Location in HEALPix directory tree: `src/idl/toolkit/ud_grade.pro`

This IDL facility provides a means to upgrade/degrade or re-order a full sky or cut-sky **HEALPix** map contained in a FITS file or loaded in memory.

FORMAT IDL> UD_GRADE , Map_in, Map_out [,
BAD_DATA=, HELP=, NSIDE_OUT=, OR-
DER_IN=, ORDER_OUT=, /PESSIMISTIC]

QUALIFIERS

Map_in	input map: either a character string with the name of a FITS file containing a full-sky or cut-sky Healpix data set, or a memory vector (real, integer, ...) containing a <i>full sky</i> data set.
Map_out	reordered map: if map_in was a filename, map_out should be a filename, otherwise map_out should point to a memory array

KEYWORDS

BAD_DATA =	flag value of missing pixels. (default: <code>!healpix.bad_value</code> $\equiv -1.6375 \times 10^{30}$).
/HELP	if set, the documentation header is printed out and the code exits
NSIDE_OUT =	output resolution parameter, can be larger or smaller than the input one (scalar integer). (default: same as input: map unchanged or simply reordered)
ORDER_IN =	input map ordering (either 'RING' or 'NESTED') (default: same as the input FITS keyword ORDERING if applicable).
ORDER_OUT =	output map ordering (either 'RING' or 'NESTED') (default: same as ORDER_IN).

/PESSIMISTIC if set, during **degradation** each big pixel containing one bad or missing small pixel is also considered as bad,
 if not set, each big pixel containing at least one good pixel is considered as good (optimistic) default = 0 (:not set)

DESCRIPTION ud_grade can upgrade/degrade a **HEALPix** map using the hierarchical properties of **HEALPix** . It can also reorder a sky map (from NEST to RING and vice-versa). It operates on FITS files as well as on memory variables. Cut-sky operations are only accessible via FITS files. The degradation/upgradation is done assuming an intensive quantity (like temperature) that does not scale with surface area. In case of degradation a big pixel that contains at least one bad small pixel is considered as bad itself. When operating on FITS files, the header information from the input file that is not directly related the ordering/resolution is copied unchanged into the output file.

RELATED ROUTINES

This section lists the routines related to **ud_grade**.

idl	version 6.1 or more is necessary to run ud_grade .
reorder	reorder a full sky Healpix map.

EXAMPLES: #1

```
ud_grade , 'map_512.fits', 'map_256.fits', nside_out = 256
```

ud_grade reads the FITS file map_512.fits (that allegedly contains a map with NSIDE=512), and write in the FITS file map_256.fits a map degraded to resolution 256, with the same ordering.

EXAMPLES: #2

```
ud_grade , 'map_512.fits', 'map_Nest256.fits', nside_out = 256, $
order_out = 'NESTED'
```

ud_grade reads the FITS file map_512.fits (that allegedly contains a map with NSIDE=512), and writes in the FITS file map_Nest256.fits a map degraded to resolution 256, with NESTED ordering.

EXAMPLES: #3

```
read_fits_map, 'map_Nest256.fits', mymap  
ud_grade , mymap, mymap2, nside_out = 1024, order_in='NESTED', order_out='RING'
```

mymap is IDL variable containing a **HEALPix** NESTED-ordered map with resolution nside=256. ud_grade upgrades this map to a resolution of 1024, reorder it to RING and write it in the IDL vector mymap2.

vec2ang

Location in HEALPix directory tree: `src/idl/toolkit/vec2ang.pro`

This IDL facility convert the 3D position vectors of points into their angles on the sphere.

FORMAT IDL> VEC2ANG , Vector, Theta, Phi [, ASTRO=]

QUALIFIERS

Vector	input, array, three dimensional cartesian position vector (x, y, z) (not necessarily normalised). The north pole is $(0, 0, 1)$. The coordinates are ordered as follows $x(0), \dots, x(n-1)$, $y(0), \dots, y(n-1)$, $z(0), \dots, z(n-1)$
Theta	output, vector, vector, colatitude in radians measured southward from north pole in $[0, \pi]$ (mathematical coordinates). If ASTRO is set, Theta is the latitude in degrees measured northward from the equator, in $[-90, 90]$ (astronomical coordinates).
Phi	output, vector, longitude in radians measured eastward, in $[0, 2\pi]$ (mathematical coordinates). If ASTRO is set, Phi is the longitude in degree measured eastward, in $[0, 360]$ (astronomical coordinates).

KEYWORDS

ASTRO =	if set Theta and Phi are the latitude and longitude in degrees (astronomical coordinates) instead of the colatitude and longitude in radians (mathematical coordinates).
---------	--

DESCRIPTION `vec2ang` performs the geometrical transform from the 3D position vectors (x, y, z) of points into their angles (θ, ϕ) on the sphere: $x = \sin \theta \cos \phi$, $y = \sin \theta \sin \phi$, $z = \cos \theta$

RELATED ROUTINES

This section lists the routines related to **`vec2ang`** .

<code>idl</code>	version 6.1 or more is necessary to run <code>vec2ang</code> .
<code>pix2xxx</code> , ...	conversion between vector or angles and pixel index
<code>ang2vec</code>	conversion from angles to position vectors

EXAMPLE:

write_fits_cut4

Location in HEALPix directory tree: `src/idl/fits/write_fits_cut4.pro`

This IDL facility writes out a cut sky **HEALPix** map into a FITS file according to the **HEALPix** convention. The format used for the FITS file follows the one used for Boomerang98 and is adapted from COBE/DMR. This routine can be used to store polarized maps, where the information relative to the Stokes parameters I, Q and U are placed in extension 0, 1 and 2 respectively by successive invocation of the routine.

FORMAT IDL> WRITE_FITS_CUT4 , File, Pixel, Signal [, N_Obs, Serror, COORDSYS=, EXTENSION=, HDR=, /NESTED, NSIDE=, ORDERING=, /POLARISATION, /RING, UNITS=, XHDR=]

QUALIFIERS

File	name of a FITS file in which the map is to be written
Pixel	(LONG or LONG64 vector), index of observed (or valid) pixels
Signal	(FLOAT or DOUBLE vector, same size as Pixel), value of signal in each observed pixel
N_Obs	(LONG or INT or LONG64 vector, Optional, same size as Pixel), number of observation per pixel. If absent, the field <code>N_OBS</code> will take a value of 1 in the output file. If set to a scalar constant, <code>N_OBS</code> will take this value in the output file
Serror	(FLOAT or DOUBLE vector, Optional, same size as Pixel) rms of signal in pixel, for white noise, this is $\propto 1/\sqrt{n_obs}$ If absent, the field <code>SERROR</code> will take a value of

0.0 in the output file. If set to a scalar constant, **SERROR** will take this value in the output file

KEYWORDS

COORDSYS=	(optional), if set to either 'C', 'E' or 'G', specifies that the Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The relevant keyword is then added/updated in the extension header, but the map is NOT rotated)
EXTENSION=	(optional), (0 based) extension number in which to write data. (default: 0). If set to 0 (or not set) <i>a new file is written from scratch</i> . If set to a value larger than 1, the corresponding extension is added or updated, as long as all previous extensions already exist. All extensions of the same file should use the same ORDERING, NSIDE and COORDSYS.
HDR=	(optional), String array containing the information to be put in the primary header.
/NESTED	if set, specifies that the map is in the NESTED ordering scheme see also: Ordering and Ring
NSIDE=	(optional), scalar integer, HEALPix resolution parameter of the data set. The resolution parameter should be made available to the FITS file, either thru this qualifier, or via the header (see XHDR).
ORDERING=	(optional), if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or NESTED ordering scheme see also: Nested and Ring The ordering information should be made available to the FITS file, either thru a combination of Ordering/Ring/Nested, or via the header (see XHDR).
/POLARISATION	specifies that file will contain the I, Q and U polarisation Stokes parameter in extensions 0, 1 and

	2 respectively, and sets the FITS header keywords accordingly
/RING	if set, specifies that the map is in the RING ordering scheme see also: Ordering and Nested
UNITS=	(optional), string describing the physical units of the data set (only applies to Signal and Serror)
XHDR=	(optional), String array containing the information to be put in the extension header.

DESCRIPTION

RELATED ROUTINES

This section lists the routines related to **write_fits_cut4** .

idl	version 6.1 or more is necessary to run write_fits_cut4
read_fits_cut4	This HEALPix IDL facility can be used to read in maps written by write_fits_cut4 .
write_fits_cut4 , write_fits_map write_tqu , write_fits_sb	HEALPix IDL routines to write cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets into FITS files
sxaddpar	This IDL routine (included in HEALPix package) can be used to update or add FITS keywords to the header in HDR and XHDR

EXAMPLES: #1

```
write_fits_cut4 , 'map_cut.fits', pixel, temperature, /ring, nside=32, /pol
```

writes in 'map_cut.fits' a FITS file containing the temperature measured in a set of **HEALPix** pixel.

EXAMPLES: #2

```
write_fits_cut4 , 'tqu_cut.fits', pixel, temperature, n_t, s_t, $  
    /ring, nside=32, /pol  
write_fits_cut4 , 'tqu_cut.fits', pixel, qstokes, n_q, s_q, $  
    /ring, nside=32, /pol, ext=1  
write_fits_cut4 , 'tqu_cut.fits', pixel, ustokes, n_u, s_u, $  
    /ring, nside=32, /pol, ext=2
```

writes in 'tqu_cut.fits' a FITS file with three extensions, each of them containing information on the observed pixel, the measured signal, the number of observations and noise per pixel, for the three Stokes parameters I, Q and U respectively. The **HEALPix** ring ordered scheme and the resolution $N_{\text{side}} = 32$ is assumed.

write_fits_map

Location in HEALPix directory tree: `src/idl/fits/write_fits_map.pro`

This IDL facility writes out a **HEALPix** map into a FITS file according to the **HEALPix** convention

FORMAT IDL> WRITE_FITS_MAP , File, T_sky,
 [Header, Coordsys=, Error=, Help=, Nested=,
 Ring=, Ordering=, Units=]

QUALIFIERS

File	name of a FITS file in which the map is to be written
T_sky	variable containing the HEALPix map
Header	(optional), string variable containing on input the information to be added to the extension header. (If already present, FITS reserved keywords will be automatically updated).
Coordsys=	(optional), if set to either 'C', 'E' or 'G', specifies that the Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The relevant keyword is then added/updated in the extension header, but the map is NOT rotated)
Error=	(optional output), will take value 1 if file can not be written
Ordering=	(optional), if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or NESTED ordering scheme see also: Nested and Ring
Units=	(optional), string describing the physical units of the data set

KEYWORDS

Help	if set, an extensive help is displayed and no file is written
Nested	if set, specifies that the map is in the NESTED ordering scheme see also: Ordering and Ring
Ring	if set, specifies that the map is in the RING ordering scheme see also: Ordering and Nested

DESCRIPTION `write_fits_map` writes out the full sky **HEALPix** map `T_sky` into the FITS file `File`. Extra information about the map can be given in `Header` according to the FITS header conventions. Coordinate systems can also be specified by `Coordsys`. Specifying the ordering scheme is compulsory and can be done either in `Header` or by setting `Ordering` or `Nested` or `Ring` to the correct value. If `Ordering` or `Nested` or `Ring` is set, its value overrides what is given in `Header`.

RELATED ROUTINES

This section lists the routines related to `write_fits_map`.

idl	version 6.1 or more is necessary to run <code>write_fits_map</code>
<code>read_fits_map</code>	This HEALPix IDL facility can be used to read in maps written by <code>write_fits_map</code> .
<code>sxaddpar</code>	This IDL routine (included in HEALPix package) can be used to update or add FITS keywords to <code>Header</code>
<code>reorder</code>	This HEALPix IDL routine can be used to reorder a map from NESTED scheme to RING scheme and vice-versa.
<code>write_fits_cut4</code> , <code>write_fits_map</code> <code>write_tqu</code> , <code>write_fits_sb</code>	HEALPix IDL routines to write cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets into FITS files
<code>write_fits_sb</code>	routine to write multi-column binary FITS table

EXAMPLE:

```
write_fits_map, 'file.fits', map, coordsys='G', ordering='ring'
```

write_fits_map writes out the RING ordered map `map` in Galactic coordinates into the file `file.fits`.

write_fits_sb

Location in HEALPix directory tree: `src/idl/fits/write_fits_sb.pro`

This IDL facility writes out a **HEALPix** map into a FITS file according to the **HEALPix** convention. It can also write an arbitray data set into a FITS binary table

FORMAT IDL> WRITE_FITS_SB , File, Prim_Stc
 [, Xten_stc, Coordsys=, /Nested, /Ring,
 Ordering=, /Partial, Nside=, Extension=,
 /Nohealpix]

QUALIFIERS

File	name of a FITS file in which the map is to be written
Prim_stc	IDL structure containing the following fields: - primary header - primary image Set it to 0 to get an empty primary unit
Xten_stc	(optional), IDL structure containing the following fields: - extension header - data column 1 - data column 2 ... NB: because of some astron routines limitation, avoid using the single letters 'T' or 'F' as tagnames in the structures Prim_stc and Xten_stc.

KEYWORDS

Coordsys= (optional),
 if set to either 'C', 'E' or 'G', specifies that the
 Healpix coordinate system is respectively Celes-
 tial=equatorial, Ecliptic or Galactic. (The rele-
 vant keyword is then added/updated in the ex-

	tension header, but the map is NOT rotated)
Ordering=	(optional), if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or NESTED ordering scheme see also: Nested and Ring
Nside=	(optional), scalar integer, HEALPix resolution parameter of the data set. Must be used when the data set does not cover the whole sky
Extension=	(optional), scalar integer, extension in which to write the data (0 based). (default: 0)
/Nested	(optional), if set, specifies that the map is in the NESTED ordering scheme see also: Ordering and Ring
/Ring	(optional), if set, specifies that the map is in the RING or- dering scheme see also: Ordering and Nested
/Partial	(optional), if set, the data set does not cover the whole sky. In that case the information on the actual map reso- lution should be given by the qualifier Nside (see above), or included in the FITS header enclosed in the Xten_stc.
/Nohealpix	(optional), if set, the data set can be arbitrary, and the re- striction on the number of pixels do not apply. The keywords Ordering , Nside , Nested , Ring and Partial are ignored.

DESCRIPTION `write_fits_sb` writes out the information contained in `Prim_stc` and `Exten_stc` in the primary unit and extension of the FITS file `File` respectively. Coordinate systems can also be specified by `Coordsys`. Specifying the ordering scheme is compulsory for **HEALPix** data sets and can be done either in `Header` or by setting `Ordering` or `Nested` or `Ring` to the correct value. If `Ordering` or `Nested` or `Ring` is set, its value overrides what is given in `Header`.

The data is assumed to represent a full sky data set with the number of data points $\text{npix} = 12 * \text{Nside} * \text{Nside}$ unless `Partial` is set OR the input fits header contains `OBJECT = 'PARTIAL'`

AND

the `Nside` qualifier is given a valid value OR the FITS header contains a `NSIDE`

If `Nohealpix` is set, the restrictions on `Nside` are void.

RELATED ROUTINES

This section lists the routines related to `write_fits_sb`.

idl	version 6.1 or more is necessary to run <code>write_fits_sb</code>
<code>read_fits_map</code>	This HEALPix IDL facility can be used to read in maps written by <code>write_fits_sb</code> .
<code>read_fits_s</code>	This HEALPix IDL facility can be used to read into an IDL structure maps written by <code>write_fits_sb</code> .
<code>sxaddpar</code>	This IDL routine (included in HEALPix package) can be used to update or add FITS keywords to the header in <code>Prim_stc</code> and <code>Exten_stc</code>
<code>write_fits_cut4</code> , <code>write_fits_map</code> <code>write_tqu</code> , <code>write_fits_sb</code>	HEALPix IDL routines to write cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets into FITS files
<code>write_tqu</code>	This HEALPix IDL facility based on <code>write_fits_sb</code> is designed to write temperature+polarization (T,Q,U) maps

EXAMPLE:

```
npix = nside2npix(128)
f= randomn(seed,npix)
n= lindgen(npix)+3
map_FN = create_struct('HDR',[' '], 'FLUX',f, 'NUMBER',n)
write_fits_sb, 'map_fluxnumber.fits', 0, map_FN, coord='G', /ring
```

The structure map_FN is defined to contain a fictitious Flux+number map, where one field is a float and the other an integer. write_fits_sb writes out the contents of map_FN into the extension of the FITS file 'map_fluxnumber.fits'.

write_tqu

Location in HEALPix directory tree: `src/idl/fits/write_tqu.pro`

This IDL facility writes a temperature+polarization Healpix map (T,Q,U) into a binary table FITS file, with optionally the error (dT,dQ,dU) and correlation (dQU, dTU, dTQ) in separate extensions

FORMAT IDL> WRITE_TQU , File, TQU, [Coordsys=, Nested=, Ring=, Ordering=, Error=, Extension=, Help=, Hdr=, Xhdr=, Units=, Help=]

QUALIFIERS

File	name of a FITS file in which the maps are to be written
TQU	<p>array of Healpix maps of size ($N_{\text{pix}}, 3, \text{n_ext}$) where N_{pix} is the total number of Healpix pixels on the sky, and $\text{n_ext} \leq 3$.</p> <p>Three maps are written in each extension of the FITS file :</p> <ul style="list-style-type: none"> -the temperature+polarization Stokes parameters maps (T,Q,U) in extension 0 -the error maps (dT,dQ,dU) (if $\text{n_ext} \geq 2$) in extension 1 -the correlation maps (dQU, dTU, dTQ) (if $\text{n_ext} = 3$) in extension 2 <p>it is also possible to write 3 maps directly in a given extension (provided the preceding extension, if any, is already filled in) by setting Extension to the extension number in which to write (0 based) and if $\text{n_ext} + \text{Extension} \leq 3$</p>
Coordsys=	<p>(optional),</p> <p>if set to either 'C', 'E' or 'G', specifies that the Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The relevant keyword is then added/updated in the extension header, but the map is NOT rotated)</p>

Error=	(optional output), will take value 1 if file can not be written
Extension=	(optional), extension unit a which to put the data (0 based). The physical interpretation of the maps is determined by the extension in which they are written see also: TQU
Hdr=	(optional), string variable containing on input the information to be added to the primary header. (If already present, FITS reserved keywords will be automatically updated).
Ordering=	(optional), if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or NESTED ordering scheme see also: Nested and Ring
Units=	(optional), string describing the physical units of the data set
Xhdr=	(optional), string variable containing on input the information to be added to the extension headerx. (If already present, FITS reserved keywords will be automatically updated). It will be repeated in each extension, except for TTYPE* and EXTNAME which are generated by the routine and depend on the extension

KEYWORDS

Help	if set, an extensive help is displayed and no file is written
Nested	if set, specifies that the map is in the NESTED ordering scheme see also: Ordering and Ring
Ring	if set, specifies that the map is in the RING ordering scheme see also: Ordering and Nested

DESCRIPTION `write_tqu` writes out Stokes parameters (T,Q,U) maps for the whole sky into a FITS file. It is also possible to write the error per pixel for each map and the correlation between fields, as subsequent extensions of the same FITS file (see qualifiers above). Therefore the file may have up to three extensions with three maps in each. Extensions can be written together or one by one (in their physical order) using the Extension option

RELATED ROUTINES

This section lists the routines related to **write_tqu**.

idl	version 6.1 or more is necessary to run <code>write_tqu</code>
<code>read_tqu</code>	This HEALPix IDL facility can be used to read in maps written by <code>write_tqu</code> .
<code>read_fits_s</code>	This HEALPix IDL facility can be used to read into an IDL structure maps written by <code>write_tqu</code> .
<code>sxaddpar</code>	This IDL routine (included in HEALPix package) can be used to update or add FITS keywords to the header(s) HDR or XHDR
<code>write_fits_cut4</code> , <code>write_fits_map</code> <code>write_tqu</code> , <code>write_fits_sb</code>	HEALPix IDL routines to write cut-sky maps, full-sky maps, polarized full-sky maps and arbitrary data sets into FITS files

EXAMPLE:

```
npix = nside2npix(64)
TQU = randomn(seed,npix,3)
write_tqu, 'map_polarization.fits', TQU, coord='G', /ring
```

The array TQU is defined to contain a fictitious polarisation map, with the 3 Stokes parameters T, Q and U. The map is assumed to be in Galactic coordinates, with a RING ordering of the pixels and $N_{\text{side}} = 64$. `write_tqu` writes out the contents of TQU into the extension of the FITS file 'map_polarization.fits'.